

SMART NotebookTM 14

Windows® operating systems

User's guide



Trade-mark notice

SMART Notebook, SMART Document Camera, SMART Ink, SMART Board, SMART Response, SMART Exchange, smarttech, the SMART logo and all SMART taglines are trade-marks or registered trade-marks of SMART Technologies ULC in the US and/or other countries. Windows, PowerPoint and Internet Explorer are either registered trade-marks or trade-marks of Microsoft Corporation in the US and/or other countries. Mac, Mac OS, OS X and QuickTime are trade-marks of Apple Inc., registered in the US and other countries. Adobe, Reader and Flash are either registered trade-marks of Adobe Systems Incorporated in the US and/or other countries. All other third-party product and company names may be trade-marks of their respective owners.

Copyright notice

© 2014 SMART Technologies ULC. All rights reserved. No part of this publication may be reproduced, transmitted, transcribed, stored in a retrieval system or translated into any language in any form by any means without the prior written consent of SMART Technologies ULC. Information in this manual is subject to change without notice and does not represent a commitment on the part of SMART.

This product and/or use thereof covered by one or more of the following US patents.

www.smarttech.com/patents

06/2014

Contents

Chapter 1: Getting started with SMART Notebook software	
About SMART Notebook software	2
About the other SMART software on your computer	2
What's new	3
Starting SMART Notebook software	3
Navigating the user interface	3
Viewing tool change notifications	9
Using gestures	9
Undoing and redoing actions	11
Chapter 2: Creating and working with files	13
Creating files	13
Opening files	13
Saving files	14
Exporting files	15
Printing files	17
Saving files automatically	18
Attaching files to email messages	21
Chapter 3: Creating and working with pages	23
Displaying pages in a file	23
Creating pages	24
Cloning pages	25
Extending pages	25
Renaming pages	26
Rearranging pages	26
Grouping pages	27
Deleting pages	28
Chapter 4: Creating basic objects	31
Writing, drawing and erasing digital ink	32
Creating shapes and lines	35
Creating text	38
Creating tables	44
Chapter 5: Working with objects	53
Selecting objects	53
Changing objects' properties	55
Positioning objects	58
Cutting, copying and pasting objects	62
Cropping images with a mask	63
Cloning objects	64

CONTENTS

Resizing objects	65
Rotating objects	67
Flipping objects	68
Grouping objects	68
Deleting objects	70
Chapter 7: Inserting, organising and sharing content	71
Inserting content from the Gallery	71
Inserting content from GeoGebra	
Inserting content from the SMART Exchange website	76
Inserting content from other sources	76
Inserting equations with the Maths Editor	86
Inserting Internet browsers	87
Attaching files and webpages	89
Organising and sharing content using the Gallery	90
Sharing content using the SMART Exchange website	95
Chapter 9: Creating lesson activities	97
Using advanced object features	98
Using advanced page features	
Creating example lesson activities	
Accessing XC Collaboration	
Chapter 10: Presenting lesson activities and facilitating collaboration	117
Preparing before presenting	
Using presentation tools whilst presenting	
Clearing or resetting pages after presenting	
Enabling two people to use an interactive whiteboard	
Chapter 11: Enhancing SMART Notebook software with add-ons	147
Installing add-ons	147
Using add-ons	
Identifying missing add-ons	
Disabling and removing add-ons	
Chapter 12: Accessing RSS feeds with Notebook Connect	151
Finding, adding and deleting an RSS feed	151
Viewing RSS feed content	
Bookmarking articles	153
Inserting images and video in the drawing area	153
Chapter 13: Maintaining SMART Notebook software	155
Customising the toolbar	155
Configuring SMART Notebook software	157
Setting the language	163
Removing SMART software	164
Updating and activating SMART software	165
Sending feedback to SMART	169

CONTENTS

Chapter 14: Troubleshooting SMART Notebook software	171
Troubleshooting files	171
Troubleshooting the SMART Notebook software window and toolbar	171
Troubleshooting digital ink	172
Troubleshooting objects	173
Troubleshooting gestures	174
Index	175

Chapter 1

Getting started with SMART Notebook software

About SMAR I Notebook software	. 2
About the other SMART software on your computer	2
What's new	3
SMART Notebook 14.1 software	. 3
SMART Notebook 14 software	. 3
Starting SMART Notebook software	3
Navigating the user interface	3
Menu	. 4
Toolbar	4
Actions panel	. 4
Plug-ins panel	4
Tools panel	4
Contextual panel	4
Customising the toolbar	5
Page Sorter	5
Opening the Page Sorter	5
Customising the Page Sorter	5
Gallery tab	. 6
Opening the Gallery tab	
Customising the Gallery tab	
Attachments tab	6
Opening the Attachments tab	
Customising the Attachments tab	
Properties tab	
Opening the Properties tab	
Customising the Properties tab	
Add-ons tab	
Opening the Add-ons tab	
Customising the Add-ons tab	
SMART Response tab	8
Page area	
Viewing tool change notifications	
Using gestures	
Undoing and redoing actions	11

This chapter introduces you to SMART Notebook™ collaborative learning software and explains how to get started with the software.

About SMART Notebook software

In SMART Notebook software, you can create .notebook files that include graphics, text, tables, lines, shapes, animations and more. Present your file and keep your class's attention as you move and interact with these objects. When your class provides comments and suggestions, write their input on the page using digital ink. You can open .notebook files in SMART Notebook software on a Windows®, Mac or Linux® computer. You can also export your file in a variety of formats, including HTML and PDF.

You can install SMART Notebook Tools as well as third-party add-ons to add special features to SMART Notebook software. SMART Notebook Tools include the following:

- 3D Tools for SMART Notebook software
- Mixed Reality Tools for SMART Document Camera™
- SMART Notebook Maths Tools

About the other SMART software on your computer

Your computer might include the following other SMART software.

SMART Product Drivers

Your interactive product detects contact with its screen and sends each contact point, along with Pen tool information, to the connected computer. SMART Product Drivers translates the information into mouse clicks and digital ink. SMART Product Drivers enables you to perform normal computer operations by using your finger or a pen.

SMART Ink™

Using SMART Ink, you can write or draw on the screen in digital ink using a pen and then save or erase your notes.

SMART Board® Tools

You can draw attention to specific parts of a page using SMART Board Tools, such as the Screen Shade, Spotlight, Magnifier and Pointer.

What's new

Education Software 2014 introduces the following new features.

SMART Notebook 14.1 software

Feature	Topic
Maths Editor	Inserting equations with the Maths Editor on page 86
Tool change notifications	Viewing tool change notifications on page 9

SMART Notebook 14 software

Feature	Topic
Paint Brush pen type	Writing or drawing digital ink on page 32
Crop images	Cropping images with a mask on page 63
Notebook Connect	Accessing RSS feeds with Notebook Connect on page 151
GeoGebra add-on	Inserting content from GeoGebra on page 75
Ink editing	Using the Text Pen on page 130
XC Collaboration add-on	Accessing XC Collaboration on page 115
Calligraphic pen type	Writing or drawing digital ink on page 32

Starting SMART Notebook software

Start SMART Notebook software by double-clicking the SMART Notebook 11 icon on the desktop.

When you start SMART Notebook software the first time, a tutorial file opens automatically. You can read the contents of this file to learn more about the software and the new features in the latest release. When you've finished, select File > New to create a new, blank file.



NOTE

When you start the software subsequent times, a new, blank file opens automatically. To open the tutorial file, select Help > Tutorial.

Navigating the user interface

The SMART Notebook software user interface consists of the following components:

- Menu
- Toolbar

Getting started with SMART Notebook software

- Tabs (Page Sorter, Gallery, Attachments, Properties, Add-ons and SMART Response™)
- Page area

Menu

The menu contains all the commands you can use to manipulate files and objects in SMART Notebook software.

Toolbar

The toolbar enables you to select and use a variety of commands. The buttons on the toolbar are organised in panels.

Actions panel

The *Actions* panel of the toolbar includes buttons that enable you to browse and make changes to .notebook files:



Plug-ins panel

If you install SMART Notebook Tools such as SMART Notebook Math Tools and SMART Response software, an additional panel appears to the right of the *Actions* panel:




Tools panel

The *Tools* panel includes buttons that enable you to create and work with basic objects on pages:



Contextual panel

When you select one of the buttons in the *Tools* panel, additional buttons appear. For example, if you select **Pens W**, the following additional buttons appear:



Press the **Pen Types** button to select a pen type and then press one of the line type buttons to write or draw digital ink in that line type. You can customise a selected line type using the options in the Properties tab and then save your changes for future use (see *Saving tool settings* on page 58).

The three property selectors beside the line type buttons enable you to set the colour, thickness, style and transparency of digital ink.

If you click any of the other buttons in the *Tools* panel, similar sets of additional buttons appear.

Customising the toolbar

You can add, remove and change the position of buttons on the toolbar by pressing **Customise the toolbar** • (see *Customising the toolbar* on page 155).

By default, the toolbar appears at the top of the SMART Notebook software window. However, you can move it to the bottom of the window by pressing **Move toolbar to top/bottom of window**. This is useful in situations where you or your students can't reach the toolbar when it's at the top of the window.

Page Sorter

The Page Sorter displays all of the pages in the open file as thumbnails and automatically updates these thumbnails as you change the contents of the pages.

Using the Page Sorter, you can do the following:

- Display pages
- Create pages
- Clone pages
- Clear pages
- Delete pages
- Rename pages
- Rearrange pages
- · Move objects from one page to another
- Group pages

Opening the Page Sorter

To open the Page Sorter, press Page Sorter .

Customising the Page Sorter

You can move the Page Sorter from one side of the SMART Notebook software window to the other by pressing **Move Sidebar** .

Getting started with SMART Notebook software

You can resize the Page Sorter by dragging its border left or right. You can also hide the Page Sorter when you aren't using it by selecting the Auto-hide tickbox. (To display the Page Sorter when it's hidden, press Page Sorter .)



NOTE

If you reduce the Page Sorter to its minimum size, the auto-hide feature turns on automatically.

Gallery tab

The Gallery tab contains clip art, backgrounds, multimedia content, files and pages that you can use in your lessons, and displays preview images of this content. The Gallery tab also provides access to other online resources. For more information, see Inserting content from the Gallery on page 71.

You can also include your own content and content from other teachers in your school in the Gallery tab (see Organising and sharing content using the Gallery on page 90).

Opening the Gallery tab

To open the Gallery tab, press Gallery .

Customising the Gallery tab

You can move the Gallery tab from one side of the SMART Notebook software window to the other by pressing Move Sidebar .

You can resize the Gallery tab by dragging its border left or right. You can also hide the Gallery tab when you aren't using it by selecting the Auto-hide tickbox. (To display the Gallery tab when it's hidden, press Gallery .)



NOTE

If you reduce the Gallery tab to its minimum size, the auto-hide feature turns on automatically.

Attachments tab

The Attachments tab displays the files and webpages attached to the current file. For more information, see Attaching files and webpages on page 89.

Opening the Attachments tab

To open the Attachments tab, press **Attachments** .

Customising the Attachments tab

You can move the Attachments tab from one side of the SMART Notebook software window to the other by pressing **Move Sidebar** .

Getting started with SMART Notebook software

You can resize the Attachments tab by dragging its border left or right. You can also hide the Attachments tab when you aren't using it by selecting the Auto-hide tickbox. (To display the Attachments tab when it's hidden, press **Attachments** .)



NOTE

If you reduce the Attachments tab to its minimum size, the auto-hide feature turns on automatically.

Properties tab

The Properties tab enables you to format objects on a page, including digital ink, shapes, lines, text and tables. Depending on the object that you select, you can change the following:

- · The colour, thickness and style of lines
- The transparency and fill effects of objects
- . The font type, size and style of text
- The animation of objects

The Properties tab displays only the options that are available for the object you select. For more information on displaying and setting object properties in the Properties tab, see Changing objects' properties on page 55.

The Properties tab also includes a Page Recording button. You can use this feature to record your actions on the current page (see Recording pages on page 105).

Opening the Properties tab

To open the Properties tab, press **Properties**

Customising the Properties tab

You can move the Properties tab from one side of the SMART Notebook software window to the other by pressing Move Sidebar .

You can resize the Properties tab by dragging its border left or right. You can also hide the Properties tab when you aren't using it by selecting the Auto-hide tickbox. (To display the Properties tab when it's hidden, press **Properties** ...)



NOTE

If you reduce the Properties tab to its minimum size, the auto-hide feature turns on automatically.

Add-ons tab

The Add-ons tab enables you to work with SMART Notebook software add-ons (see Enhancing SMART Notebook software with add-ons on page 147).

Getting started with SMART Notebook software

Opening the Add-ons tab

To open the Add-ons tab, press Add-ons de.

Customising the Add-ons tab

You can move the Add-ons tab from one side of the SMART Notebook software window to the other by pressing Move Sidebar .

You can resize the Add-ons tab by dragging its border left or right. You can also hide the Add-ons tab when you aren't using it by selecting the Auto-hide tickbox. (To display the Add-ons tab when it's hidden, press **Add-ons 4**.)



NOTE

If you reduce the Add-ons tab to its minimum size, the auto-hide feature turns on automatically.

SMART Response tab

The SMART Response tab is part of SMART Response software and is available only if you have SMART Response software installed.

Page area

The page area displays the contents of a selected page in a file. This is the area of the page where you create and work with objects (see Creating basic objects on page 31).

Viewing tool change notifications

If your SMART product has Touch Recognition enabled, SMART Notebook software displays tool change notifications when you select a new hardware tool or change a tool's settings. Pens, the eraser and the mouse are all hardware tools. You can also view tool change notifications when you touch the display with your finger.



NOTE

Only some SMART hardware products support Touch Recognition. For more information, refer to your SMART hardware product's user guide.

To view tool change notifications

Using a hardware tool or your finger, press the toolbar to select tool settings.

A status bar appears under the toolbar and shows the active tool and settings. The status bar updates each time that you select another tool or setting.






NOTE


The status bar also appears when you assign ink settings to the hardware pen using the Properties tab (see Changing objects' properties on page 55).

Using gestures


You can interact with objects in SMART Notebook software using the following gestures (if supported by your interactive product):




Swipe (left to right)




Swipe (right to left)




Pinch to zoom in / scale (enlarge)




Pinch to zoom out / scale (reduce)




Pan



Rotate







Flick

Undoing and redoing actions

When you make changes to a file, you can reverse the effects of your previous actions and commands.



NOTE

If two people are using your interactive product, pressing **Undo** and **Redo** affects the actions of both users.

To reverse the effect of the last action

Press **Undo** 5.



NOTE

You can undo an unlimited number of actions.

To reinstate the last action reversed with the Undo command

Press Redo C.

Chapter 2

Creating and working with files

Creating files	
Opening files	13
Saving files	14
Exporting files	15
Printing files	17
Saving files automatically	18
Attaching files to email messages	21

In SMART Notebook software, you can create or open SMART Notebook software (.notebook) files. After creating or opening a .notebook file, you can save it, print it and complete other common tasks.

Creating files

When you start SMART Notebook software for the first time, a tutorial file opens automatically. When you start the software subsequent times, a new .notebook file opens automatically. However, you can create a new file at any time.

To create a file

Select File > New.

If you're working on a file with unsaved changes, a dialogue box appears and prompts you to save the current file. Press **Yes** to save your changes and then follow the on-screen instructions.

Opening files

With SMART Notebook 11 software, you can open the following:

- .notebook files (the default file format for SMART Notebook 9.5, 9.7, 10 and 11 software)
- .xbk files (the default file format for SMART Notebook 8.x, 9.0 and 9.1 software)

Once you have opened a file, you can save the file as a .notebook file.

The method by which you open a file is the same for all versions of SMART Notebook software.

Creating and working with files

To open a file

Press Open File ¹.

The Open dialogue box appears.

- 2. Browse to and select the file.
- 3. Press Open.



You can open a recently opened file by selecting the File menu and then selecting the file name.

Saving files

By default, SMART Notebook software saves your files in .notebook format. Anyone with SMART Notebook 9.5 or later software for Windows operating systems, Mac OS X operating system software or Linux operating systems installed on his or her computer can open a .notebook file.

To save a new file

1. Press Save 💾.

The Save As dialogue box appears.

- 2. Browse to where you want to save the new file.
- 3. Type a name for the file in the File name box.
- 4. Press Save.

To save an existing file

Press Save



To save an existing file with a new name or location

1. Select File > Save As.

The Save As dialogue box appears.

- 2. Browse to where you want to save the new file.
- 3. Type a name for the file in the File name box.
- 4. Press Save.

Exporting files

You can export your .notebook files to the following formats:

- Webpages
- Picture formats
 - o BMP
 - o GIF
 - o JPEG
 - o PNG
- PowerPoint®
- PDF
- Interactive Whiteboard Common File Format (CFF)

NOTES

- SMART Notebook software doesn't include attachments when you export files as picture files. To include attachments, you must export your file as either webpages or PDF (Adobe® Reader® 6.0 or later).
- SMART Notebook software doesn't export files that you attach to your .notebook file as shortcuts. If you want to include an attachment, attach a copy of the file (see *Attaching files and webpages* on page 89).
- SMART Notebook software doesn't export some gradient, pattern and image effects. These effects might appear as a solid fill or appear incorrectly in the exported file.

You can also set SMART Notebook software to save a .notebook file in one of the above formats automatically when you display a different page or after a specified period of time (see *Saving files automatically* on page 18).

To export a file as webpages

1. Select File > Export As > Webpage.

The Save As dialogue box appears.

- 2. Browse to where you want to export the file.
- 3. Type a name for the file in the *File name* box.
- 4. Press Save.

To export a file as picture files

1. Select File > Export As > Image Files.

The Save As dialogue box appears.

- 2. Select a folder where you want to export the files.
- 3. Select a picture format in the Image Type drop-down list.
- 4. Select a picture size in the Size drop-down list.
- 5. Press OK.

To export a file as a PowerPoint file

1. Select File > Export As > PowerPoint.

The Save As dialogue box appears.

- 2. Browse to where you want to export the file.
- 3. Type a name for the file in the File name box.
- 4. Select PowerPoint 2007 Files (*.pptx) or PowerPoint Files (*.ppt) in the Save at type drop-down list.
- 5. Press Save.



NOTE

You can also import PowerPoint files (see Importing PowerPoint files on page 84).

To export a file as a PDF file

1. Select File > Export As > PDF.

The Export PDF dialogue box appears.

- 2. Press Thumbnails, Handouts or Full Page.
- 3. Optionally, type header text in the Header box, footer text in the Footer box and the current date in the Date box.
- 4. Optionally, select the Show page numbers check box to show a page number on each
- 5. If you pressed Thumbnails or Handouts in step 2, select a thumbnail size in the Thumbnail size drop-down list and, optionally, select the Page borders tickbox to show a border around each thumbnail and the Thumbnail titles tickbox to show titles under each thumbnail.

Creating and working with files

6. Select All to include all pages.

OR

Select Pages to include select pages and then type the page numbers in the box. Separate individual page numbers with commas and separate page ranges with a hyphen (for example, 1,2,4-7).

7. Press Save.

The Save as PDF File dialogue box appears.

- 8. Browse to where you want to export the file.
- 9. Type a name for the file in the File name box.
- 10. Press Save.

To export a file as a CFF file

1. Select File > Export As > CFF.

The Save As dialogue box appears.

- 2. Browse to where you want to export the file.
- 3. Type a name for the file in the *File name* box.
- 4. Press Save.



NOTE

You can also import CFF files (see Importing files from other interactive whiteboard programs on page 85).

Printing files

You can print all pages or select pages in a .notebook file. You can print the pages as thumbnails, handouts or full pages.

To print a file

1. Select File > Print.

The Print dialogue box appears.

- 2. Press Thumbnails, Handouts or Full Page.
- 3. Optionally, type header text in the Header box, footer text in the Footer box and the current date in the Date box.
- 4. Optionally, select the **Show page numbers** check box to show a page number on each page.

Creating and working with files

- 5. If you pressed **Thumbnails** or **Handouts** in step 2, select a thumbnail size in the *Thumbnail* size drop-down list and, optionally, select the Page borders tickbox to show a border around each thumbnail and the Thumbnail titles tickbox to show titles under each thumbnail.
- 6. Select All to include all pages.

OR

Select Pages to include select pages and then type the page numbers in the box. Separate individual page numbers with commas and separate page ranges with a hyphen (for example, 1,2,4-7).

- 7. Press the **Printer Setup** tab.
- 8. Specify other print settings, including the printer name and the number of copies.
- 9. Press Print.

Saving files automatically

You can manually save your .notebook files at any time (see Saving files on page 14) and export them to a variety of formats (see Exporting files on page 15). You can also set SMART Notebook software to save your file automatically when you display a different page or after a specified period of time.

NOTES

- SMART Notebook software doesn't include attachments when you export files as picture files. To include attachments, you must export your file as either webpages or PDF (Adobe Reader 6.0 or later).
- SMART Notebook software doesn't export files that you attach to your .notebook file as shortcuts. If you want to include an attachment, attach a copy of the file (see Attaching files and webpages on page 89).
- SMART Notebook software doesn't export some gradient, pattern and image effects. These effects might appear as a solid fill or appear incorrectly in the exported file.

To save a file automatically

1. Select File > Timed Saves.

The Timed Save Wizard appears.

Creating and working with files

2. Select **Every time I move to a different page** to save your file automatically every time you select a different page.

OR

Select **1 minute**, **5 minutes**, **15 minutes** or **30 minutes** to save your file automatically after a specified period of time.

- 3. Press Next.
- 4. Select Notebook Document.
- 5. Press Next.

The Save As dialogue box appears.

- 6. Browse to where you want to save the new file.
- 7. Type a name for the file in the *File name* box. SMART Notebook software automatically saves the file with the .notebook file extension.
- 8. Press Save.

To save a file automatically as webpages

1. Select File > Timed Saves.

The Timed Save Wizard appears.

Select Every time I move to a different page to export your file automatically when you display a different page.

OR

Select **1 minute**, **5 minutes**, **15 minutes** or **30 minutes** to export your file automatically after a specified period of time.

- 3. Press Next.
- 4. Select Webpage (HTML).
- 5. Press Next.

The Save As dialogue box appears.

- 6. Browse to where you want to export the file.
- 7. Type a name for the file in the File name box.
- 8. Press Save.

To save a file automatically as PDF files

1. Select File > Timed Saves.

The Timed Save Wizard appears.

Creating and working with files

Select Every time I move to a different page to export your file automatically when you display a different page.

OR

Select **1 minute**, **5 minutes**, **15 minutes** or **30 minutes** to export your file automatically after a specified period of time.

- 3. Press Next.
- 4. Select PDF.

OR

Select **Time Stamped PDFs**, if you want the exported files' names to include the time of the export.

5. Press Next.

The Save As dialogue box appears.

- 6. Browse to where you want to export the file.
- 7. Type a name for the file in the File name box.
- 8. Press Save.

To save a file automatically as picture files

1. Select File > Timed Saves.

The Timed Save Wizard appears.

Select Every time I move to a different page to export your file automatically when you display a different page.

OR

Select 1 minute, 5 minutes, 15 minutes or 30 minutes to export your file automatically after a specified period of time.

- 3. Press Next.
- 4. Select Image Files.
- 5. Press Next.
- 6. Press **Browse**, browse to where you want to export the files and then press **Open**.
- 7. Select the picture format in the *Image Type* drop-down list.
- 8. Select the picture size in the Size drop-down list.
- 9. Press OK.

To save a file automatically as a PowerPoint file

1. Select File > Timed Saves.

The Timed Save Wizard appears.

Select Every time I move to a different page to export your file automatically when you display a different page.

OR

Select 1 minute, 5 minutes, 15 minutes or 30 minutes to export your file automatically after a specified period of time.

- 3. Press Next.
- 4. Select PowerPoint.
- 5. Press Next.

The Save As dialogue box appears.

- 6. Browse to where you want to export the file.
- 7. Type a name for the file in the File name box.
- 8. Press Save.

To cancel automatic file saving

1. Select File > Timed Saves.

The Timed Save Wizard appears.

- 2. Select Do not save the document automatically.
- 3. Press Next.

Attaching files to email messages

You can send your file to others by attaching the file, or a PDF version of the file, to an email message.

To attach a file to an email message

Select File > Send To > Mail Recipient.

Your default email program starts, creates a new message and attaches the current file to the message.

If you haven't saved the file, SMART Notebook software saves it as a temporary file called **untitled.notebook** and your email program attaches this temporary file to the email message.

Creating and working with files

To attach a file to an email message as a PDF

Select File > Send To > Mail Recipient (as PDF).

Your default email program starts, creates a new message and attaches a PDF of the current file to the message.

If you haven't saved the file, SMART Notebook software saves the PDF file as a temporary file called **untitled.pdf** and your email program attaches the temporary file to the email message.

Chapter 3

Creating and working with pages

Displaying pages in a file	
Creating pages	
Cloning pages	
Extending pages	
Renaming pages	
Rearranging pages	
Grouping pages	
Deleting pages	

A .notebook file is composed of a series of pages, each with its own objects and properties.

A thumbnail of each page appears in the Page Sorter. Using either the Page Sorter or menu commands, you can display an existing page, create a blank page, create a clone of an existing page or delete an existing page.

Displaying pages in a file

You can display any page in the file using the Page Sorter. You can display the next or previous page in the file using buttons or gestures.

To display a page


- 1. If the Page Sorter isn't visible, press **Page Sorter** .
- 2. Press the thumbnail of the page you want to display.

To display the next page in a file

Press Next Page .

OR

Swipe your finger across the page from right to left.



A message appears, displaying the current page's number.




To display the previous page in a file

Press Previous Page 룩.



Swipe your finger across the page from left to right.



A message appears, displaying the current page's number.



Creating pages

You can add a blank page to the open file using the Add Page button or the Page Sorter.

To insert a page using the Add Page button

Press Add Page 5.

The new page appears after the current page.

To insert a page using the Page Sorter

- 1. If the Page Sorter isn't visible, press **Page Sorter** .
- 2. Select the thumbnail of the page that you want the new page to appear after.

Creating and working with pages

3. Press the thumbnail's menu arrow and then select Insert Blank Page.

The new page appears after the selected page.

Cloning pages

As an alternative to creating a blank page, you can create a duplicate (or "clone") of an existing page.



NOTE

You can clone a page only if it contains content.

To clone a page

- 1. If the Page Sorter isn't visible, press Page Sorter ...
- 2. Select the thumbnail of the page that you want to clone.
- 3. Press the thumbnail's menu arrow and then select Clone Page.

The cloned page appears immediately after the current page.



NOTE

You can repeat this process as many times as you want.

Extending pages

If you need more room at the bottom of a page, you can extend the page vertically without affecting the page's width. You can turn this feature off to prevent your pages from becoming longer.

To extend a page

- 1. If you're displaying the page in Entire Page view, select a different zoom level.
- 2. Press the Extend Page link at the bottom of the page.

To turn Extend Page on or off

- 1. Select View > Extend Page
- 2. Select Off to turn the Extend Page feature off.

OR

Select **On** to turn the Extend Page feature on.

Renaming pages

When you create a page, SMART Notebook software automatically names the page with the date and time of its creation. You can change this name.

To rename a page

- 1. If the Page Sorter isn't visible, press **Page Sorter** .
- 2. Double-click the page's name.
- 3. Type a new name for the page.
- 4. Press elsewhere.

Rearranging pages

If you want, you can rearrange the order of the pages in a file.

To rearrange pages

- 1. If the Page Sorter isn't visible, press **Page Sorter** .
- 2. Press the thumbnail of the page that you want to move in the file.

A blue border appears around the thumbnail.

3. Drag the thumbnail to its new position in the Page Sorter.

A blue line indicates the page's new position.

4. Release the thumbnail.

Grouping pages

You can group pages in a file. This enables you to find a particular group quickly in the Page Sorter and then display its pages. This is useful when there are a lot of pages in a file.

To create or edit a group

- 1. If the Page Sorter isn't visible, press **Page Sorter** .
- 2. Press the first group's menu arrow and then select Edit Page Groups.

All the groups and pages for the current file are displayed. Groups appear as blue bars and pages appear as thumbnails:

- If you created and edited the groups in this file, the pages appear under the blue bars you created and renamed.
- If you haven't edited the groups, a default group titled Group 1 appears and includes all
 of the pages and their thumbnails below its blue bar.



Thumbnails below each blue bar include the same menu arrow options as thumbnails in the Page Sorter. This enables you to press a thumbnail in a group, select its menu arrow and then delete the page, clear the page, insert a new page, clone the page, rename the page, add a Screen Shade to the page or add the page to the Gallery.

3. Press the **Add New Group** button in the upper right-hand corner.

A new group, with a new, blank page, appears.

4. Type a new name for the group.

Creating and working with pages

5. Do the following:

- To move a page into a group, press the page's thumbnail and then drag it below the group's blue bar and to the right of the thumbnail that you want it to follow.
- To rearrange the order of pages in a group, press a page's thumbnail and then drag it to the right of the thumbnail that you want it to follow.
- o To rearrange the order of groups, press a group's blue bar and then drag it below the blue bar of the group that you want it to follow.



NOTES

- You can also change the order of the groups by pressing a blue bar's menu arrow and then selecting Move Up or Move Down.
- o SMART Notebook software numbers pages sequentially across a file. If you change the order of groups, SMART Notebook software renumbers the pages in the groups accordingly.
- o To delete a group and keep its pages, move all of its pages to different groups. When a group contains no pages, SMART Notebook software automatically deletes it.
- To delete a group and all pages in the group, press the blue bar's menu arrow and then select Delete Group.
- 6. Press 🖸.

To access a group in the Page Sorter

- 1. If the Page Sorter isn't visible, press Page Sorter .
- 2. Press the first group's menu arrow and then select the name of the group that you want to

The Page Sorter displays the thumbnail for the first page in the group that you want to access.

Deleting pages

You can delete a page from the current file using the Delete Page button or the Page Sorter.



As an alternative to deleting a page, you can clear all of its objects (see Clearing pages on page 141).

Creating and working with pages

To delete a page using the Delete Page button

- 1. If you haven't done so already, display the page that you want to delete.
- 2. Select **Delete Page** 3.

To delete a page using the Page Sorter

- 1. If the Page Sorter isn't visible, press **Page Sorter** .
- 2. Select the thumbnail of the page that you want to delete.
- 3. Press the thumbnail's menu arrow and then select **Delete Page**.

Chapter 4

Creating basic objects

Writing, drawing and erasing digital ink	32
Writing or drawing digital ink	32
Erasing digital ink	
Creating shapes and lines	35
Creating shapes with the Shapes tool	35
Creating shapes with the Regular Polygons tool	
Creating shapes with the Shape Recognition Pen tool	37
Creating straight lines and arcs	37
Creating text	38
Typing text	38
Converting handwriting to typed text	39
Formatting text	40
Resizing text objects	42
Inserting mathematical symbols	42
Checking the spelling of text objects	43
Cutting and pasting text	44
Creating tables	44
Creating tables	44
Pasting tables from other programs	46
Adding objects to tables	46
Selecting tables, columns, rows or cells	47
Moving tables	48
Changing a table's properties	48
Resizing tables, columns or rows	50
Adding or removing columns, rows or cells	51
Splitting or merging table cells	52
Deleting tables and the contents of tables	52

Objects are the building blocks of content in your .notebook files. An object is simply an item on a page that you create or import and then work with. Basic types of objects include the following:

- Digital ink (freehand writing and drawing)
- Shapes
- Straight lines
- Arcs

Creating basic objects

- Text
- Tables

Writing, drawing and erasing digital ink

Digital ink is freehand text or objects that you create using your interactive display's pen or pens, or the SMART Notebook software Pens tool. Writing or drawing digital ink enables you to quickly add content to your SMART Notebook software files, either when creating the files or when presenting the files to students.

Once you have created digital ink, you can erase it.

Writing or drawing digital ink

The easiest way to write or draw digital ink is to use your interactive display's pen or pens.

You can also create freehand objects using the Pens tool. The Pens tool enables you to write or draw digital ink using the following pen types:


Pen type	Purpose and example	Notes
Standard	Write or draw digital ink in a variety of colours and line styles.	Using the Standard pen type, you can write or draw digital ink that fades after a few seconds (see <i>Using the Standard pen type to create fading objects</i> on page 133).
✓ Calligraphic	Write or draw digital ink, like you do with the Standard pen type, but with lines of varying thickness.	The Calligraphic pen type is useful for teaching students handwriting.
Crayon	Write or draw crayon-like digital ink.	The Crayon pen type is intended for artistic work, such as painting and colouring pictures, rather than writing.
Highlighter	Highlight text and other objects.	

Pen type	Purpose and example	Notes
ABC Text	Write notes that automatically convert to editable text.	You can edit your text as you work without touching a
	SMART⊘⊗	keyboard (see <i>Using the Text Pen</i> on page 130).
Creative	Add colourful elements to your presentations.	You can create custom Creative pen styles (see Creating custom Creative pen styles on page 98).
Paint Brush	Write or draw paint-like digital ink.	The Paint Brush pen type is intended for artistic work, such as painting and colouring pictures, rather than writing.
M Agic	Write or draw digital ink that fades after a few seconds.	You can also use the Magic Pen to open a magnification window or a spotlight window (see <i>Using the Magic Pen</i> on page 127).
Shape Recognition	Draw a variety of shapes with digital ink.	You can draw circles, ovals, squares, rectangles, triangles and arcs (see <i>Creating shapes with the Shape Recognition Pen tool</i> on page 37).

To write or draw digital ink

1. Press Pens W.

The Pens tool buttons appear.



- 2. Press **Pen Types** and then select a pen type.
- 3. Select a line type.

Creating basic objects

4. Optionally, customise the line type using the property selectors.



NOTE

You can also customise the line type using the Properties tab (see Changing objects' properties on page 55).

5. Write or draw digital ink on the page.

TIPS

- o Don't rest your elbow or the palm of your hand on your interactive product's surface whilst you write or draw.
- If you write or draw multiple lines, SMART Notebook software automatically combines the lines into a single object. For example, if you write the letters of a word, SMART Notebook software combines the individual letters, enabling you to interact with the whole word. If you want to write words on the same line but don't want them combined, leave a large gap between them, use different pens, or briefly put the pen in the pen tray before writing another word (interactive whiteboards only).
- o If you want to write diagonally, write in a straight line, and then rotate it (see Rotating objects on page 67).
- If you want to write in small letters, write large letters, and then reduce their size (see Resizing objects on page 65).
- You can fill areas that you've enclosed with digital ink (see Filling digital ink drawings) on page 57).

Erasing digital ink

You can erase digital ink from your interactive display using the eraser or the erasing gesture. If you're erasing digital ink from a .notebook file page, you can also erase objects using the Eraser tool.



NOTE

Although you can erase digital ink, you're unable to erase other types of objects, including shapes, lines, text and pictures. To remove these types of objects, you must delete them (see Deleting objects on page 70).

To erase digital ink

- 1. Press **Eraser** and then select an eraser type.
- 2. Erase the digital ink.

Creating shapes and lines

In addition to creating freehand shapes and lines by drawing digital ink, you can create shapes and lines using the tools in SMART Notebook software.



NOTE

To remove a shape or line from a page, you must delete it (see *Deleting objects* on page 70). The Eraser tool doesn't remove shapes.


Creating shapes with the Shapes tool

You can use the Shapes tool to create a variety of shapes, including perfect circles, perfect squares, perfect triangles, other geometric shapes, hearts, ticks and Xs.

You can add a shape to your page and then edit its properties. Alternatively, you can customise a shape's outline colour, fill colour and line thickness and then add it to your page.

To create a shape

The Shapes tool buttons appear.



2. Select a shape on the toolbar.

OR

Press ▼ and then select a shape.

3. Optionally, customise the shape using the property selectors.



NOTE

You can also customise the shape using the Properties tab (see Changing objects' properties on page 55).

Creating basic objects

4. Create a shape by pressing where you want to place the shape and dragging until the shape is the size that you want.



TIPS

- You can create perfect circles, squares, triangles and other shapes by holding down SHIFT as you draw the shape.
- You can select a shape while the Shapes tool is active without having to switch to the **Select** tool . Press the shape once and a selection rectangle appears around the shape.


Creating shapes with the Regular Polygons tool

In addition to creating shapes using the Shapes tool, you can create regular polygons with 3 to 15 sides using the Regular Polygons tool.

To create a shape with the Regular Polygons tool

Press Regular Polygons

The Regular Polygons tool buttons appear.



2. Select a shape on the toolbar.

OR

Press ▼ and then select a shape.



NOTE

The number in the shape indicates its number of sides.

3. Optionally, customise the shape using the property selectors.



NOTE

You can also customise the shape using the Properties tab (see Changing objects' properties on page 55).

4. Create a shape by pressing where you want to place the shape and dragging until the shape is the size that you want.

Creating shapes with the Shape Recognition Pen tool

You can use the Shape Recognition Pen tool to draw circles, ovals, squares, rectangles, triangles and arcs.


NOTE

You can also create shapes using the Shapes tool (see Creating shapes with the Shapes tool on page 35) or the Regular Polygons tool (see Creating shapes with the Regular Polygons tool on the previous page).

To draw a shape

1. Press **Pens 1.**

The Pens tool buttons appear.



- 2. Press Pen Types and then select Shape Recognition Pen.
- 3. Draw a shape on the page.

If SMART Notebook software recognises your drawing as a circle, oval, square, rectangle, triangle or arc, it adds this shape to the page.



Creating straight lines and arcs


You can use the Lines tool to draw straight lines and arcs.

You can add a line to your page and then edit its properties. Alternatively, you can customise the line, and then add it to your page.

To create a straight line or arc

1. Press Lines .

The Lines tool buttons appear.



- 2. Select a line or arc type.
- 3. Optionally, customise the line or arc type using the property selectors.



NOTE

You can also customise the line or arc type using the Properties tab (see Changing objects' properties on page 55).

4. Create a line by pressing where you want the line to start and dragging to where you want the line to end.

Creating text

You can create text in SMART Notebook software by doing any of the following:

- Typing the text using a keyboard connected to your computer
- · Typing the text using SMART Keyboard
- Writing the text (see Writing, drawing and erasing digital ink on page 32) and then converting it to typed text using the software's handwriting recognition feature

After creating text, you can edit it, check its spelling and change its properties, including font style, size and colour.

Typing text

You can type new text or edit existing text.

To type new text

- 1. If a keyboard isn't accessible, press the SMART Board icon on the notification area and then select Keyboard.
- Press Text △ and then select an available font style.
- 3. Optionally, customise the font style (see Formatting text on page 40).

Creating basic objects

- 4. Press where you want the text to start.
- 5. Type your text.
- 6. When you've finished, press outside the text object.

To edit existing text

- 1. Double-click the text object.
- 2. Edit the text.
- 3. When you've finished, press outside the text object.


Converting handwriting to typed text

You can write on your interactive product's screen using the Standard or Calligraphic pen types and convert your writing to typed text. SMART Notebook software can convert handwriting in multiple languages.

To convert handwriting to typed text

1. Press Pens W.

The Pens tool buttons appear.



- 2. Press Pen Types and then select Pen or Calligraphic Pen.
- 3. Write your text.



Write neat, printed characters on a horizontal line. Although SMART Notebook software can convert slanted or cursive writing, it doesn't always do so consistently.

4. Select the text object.

The SMART Notebook software handwriting recognition feature compares your written word with its dictionary and identifies words that most resemble what you've written.

Creating basic objects

5. Press the text object's menu arrow.

A menu appears and displays the list of matching words, each preceded by Recognise.



NOTES

- If you want SMART Notebook software to identify words in a different language, select Recognise Languages and then select another language in the list. SMART Notebook software updates the list of matching words to include words in the selected language.
- o If you change the handwriting recognition language, you don't change the default language of the SMART Notebook software user interface or your operating system.
- 6. Select a word in the list of matching words.

The selected word appears on the page.

Formatting text

If you want to format all text in a text object, select the text object.

OR

If you want to format specific text in a text object, double-click the text object and then select the text.

You can format text using the buttons in the toolbar or the options in the Properties tab or the Format menu.



NOTE

If the Properties tab isn't visible, press **Properties** $\stackrel{\text{def}}{=}$ and then press **Text Style**.

The following table presents the formatting changes that you can make using the above tools:

Change	Toolbar	Properties tab	Format menu
Character, paragraph or object level			
Change the font face	✓	✓	
Change the font size	✓	✓	
TIP To select a font size that doesn't appear in the drop-down list (including font sizes with decimal values such as 20.5), type the font size in the Font Size box on the toolbar.			
Change the colour	✓	✓	

Change	Toolbar	Properties tab	Format menu
Bold, italicise or underline text	✓	✓	✓
Strike out text	√ 1	✓	✓
Superscript or subscript text	√ ²	✓	✓
Paragraph or object level			
Change justification (left, right or centre)	✓	✓	✓
Change indentation	√3	✓	✓
Create a bulleted or numbered list	√ 4	✓	✓
Insert a drop cap		✓	✓
∏ TIP			
To insert a drop cap at the beginning of a paragraph, press Drop Cap in the <i>Properties</i>			
tab under Text Style.			
OR			
Select Format > Paragraph > Drop Cap.			
Change line spacing		√	√
TIP			
To add spacing between paragraphs, select the Add space after paragraphs tickbox in the Properties tab or select Format > Paragraph > Line Spacing > Add space after paragraphs.			
Change language direction (left-to-right or right-to-left)			✓
NOTE			
Select Format > Paragraph > Direction > Left to Right for languages that read left to right (for example, English and French).			
OR			
Select Format > Paragraph > Direction > Right to Left for languages that read right to left (for example, Arabic and Hebrew).			

¹Under More Text Options ♣

²Under More Text Options ♣

³Under More Text Options ♣

⁴Under More Text Options ▲

Change	Toolbar	Properties tab	Format menu
Object level			
Change text direction (horizontal or vertical)	√ 5	✓	✓
Change transparency	✓	✓	

Resizing text objects

When you resize a text object following the procedure in *Resizing objects* on page 65, the text in the object changes size.

If you want to resize the text object without changing the size of the text in the object, complete the following procedure.

To resize a text object

- 1. Double-click the text object.
- 2. Press one of the two white circles on either side of text object, and then drag the circle to increase or reduce the text object's size.

Inserting mathematical symbols

You can insert a variety of mathematical and scientific symbols into a page.



The mathematical symbols are characters only. They don't perform mathematical operations.

To insert a mathematical symbol

- 1. Type text on a page.
- Press More Text Options [♣] and then select Insert Symbol ^{√x}.
 The Insert Symbols dialogue box appears.
- 3. Press a category.

A list of symbols appears.

- 4. Press the symbol you want to add to the text.
- 5. Press Insert.

The symbol appears in the text object.

⁵Under More Text Options A

Checking the spelling of text objects

As you type text, SMART Notebook software checks the spelling. If you spell a word incorrectly, SMART Notebook software underlines the word in red. You can then right-click the word and select the correct spelling from a list of options.

If you prefer, you can disable this feature and check the spelling using the *Spelling Check* dialogue box.

To disable automatic spell checking

- 1. Press **Text A**.
- 2. Press More Text Options A and then select Check Spelling

To manually check spelling of a text object

- 1. Select the text object.
- 2. Press the object's menu arrow and then select Check Spelling.

If SMART Notebook software finds a misspelled word, the *Spelling Check* dialogue box appears. This dialogue box displays the misspelt word and suggests alternatives.

- 3. For each misspelled word, do one of the following:
 - To keep the word's current spelling for this instance, press Ignore Once.
 - To keep the word's current spelling for all instances in the file, press Ignore All.
 - To keep the word's current spelling for all instances in the file and add the spelling to the dictionary, press Add to Dictionary.
 - To change the word's spelling for this instance, select the correct word in the Suggestions list and then press Change.
 - To change the word's spelling for all instances in the file, select the correct word in the Suggestions list and then press Change All.



If you pressed a button by mistake, press **Undo** to undo the resulting change.

Once you have completed this step for each misspelled word, a dialogue box appears asking whether you want to check the spelling in the rest of the file.

4. Press Yes to check the remainder of the file.

OR

Press **No** to close the *Spelling Check* dialogue box without checking the rest of the file.

Cutting and pasting text

You can cut, copy and paste text objects like any other objects (see *Cutting, copying and pasting objects* on page 62). You can also cut and paste text in a text object.

To cut and paste text to another location on the same page

- 1. Double-click the text object.
- 2. Select the text that you want to cut.
- 3. Drag the selected text to another location on the same page.

To cut and paste text to another page

- 1. If the Page Sorter tab isn't visible, press **Page Sorter** .
- 2. Double-click the text object.
- 3. Select the text that you want to copy.
- 4. Drag the selected text to the other page's icon in the Page Sorter tab.

Creating tables

You can create tables in SMART Notebook software or paste them from other programs. Once you have created a table, you can insert objects into the table's cells.

If you want to customise a table, you can select a table, column, row, cell or selection of cells and then do any of the following:

- · Move the table
- Change line type, fill and text properties
- · Resize the table, a column or a row
- · Insert or remove columns, rows or cells
- Split or merge cells
- · Delete the table

Creating tables

To insert a table using the Table button

Press **Table** A grid appears.

Creating basic objects

2. Move the pointer over the grid to select the number of columns and rows that you want in the table.



NOTE

The cells of the grid correspond to the cells of your table.



TIP

The grid displays eight rows and eight columns by default. You can add rows by moving the pointer past the bottom row. Similarly, you can add columns by moving the pointer past the right row.

If you're using a mouse, click and hold the left mouse button whilst moving the pointer.

3. Press the screen or click your mouse.

The table appears on the page.

To insert a table using the Insert Table dialogue box

1. Select Insert > Table.

The Insert Table dialogue box appears.


- 2. Type the number of rows and columns in the boxes.
- 3. Optionally, select **Make cells square** to make the table cells square.
- 4. Optionally, select Remember dimensions for new tables to use the current table dimensions for all future tables that you create in SMART Notebook software.
- 5. Press OK.

The table appears on the page.

To draw a table

1. Press **Pens 1.**

The Pens tool buttons appear.



- 2. Press Pen Types and then select Pen or Calligraphic Pen.
- 3. Select a line type.

Creating basic objects

4. Draw a table on the screen.



Make the lines of the table as straight as possible and connect the corners.

- 5. Press Select .
- 6. Select your drawing.
- 7. Press the menu arrow and then select **Recognise Table**.

If SMART Notebook software recognises your drawing as a table, it removes your drawing and adds a table to the page.

Pasting tables from other programs

You can cut or copy a table from Word or PowerPoint and then paste it into a .notebook file. The table's formatting and layout can vary when the table appears in the .notebook file.

If you want to cut or copy more than one table, you must cut or copy each table individually.



NOTE

You can also cut or copy a table from a .notebook file and then paste it into Word or PowerPoint. However, the table's formatting and layout can vary when the table appears in Word or PowerPoint.

If you're pasting a table into PowerPoint which has cells that contain non-text objects, the nontext objects appear outside of the table in PowerPoint.

Adding objects to tables

Once you have inserted a table on a page, you can insert objects into the table's cells.



NOTE

You can add only one object to each cell. If you want to add multiple objects to a cell, do one of the following:

- Group the objects before adding them to the table (see *Grouping objects* on page 68).
- Select all of the objects at once and then add them to the table as described in the following procedure. SMART Notebook software automatically groups the objects in the table cell.

Creating basic objects

To add an object to a table

- 1. Select the object.
- 2. Drag the object to the table cell.



NOTE

You're unable to move an object if it's locked in place (see Locking objects on page 103).

The object appears in the table cell.



NOTE

If you add a text object to a table, the cell resizes to fit to the text object. If you add other object types to the table, the object resizes to fit the cell.

To remove an object from a table

- 1. Select the object.
- 2. Drag the object out of the table.

Selecting tables, columns, rows or cells

You can select a table, column, row, cell or selection of cells. Once you have selected a table or part of a table, you can do the following:

- Move the table
- · Change the table's or cells' properties
- · Resize the table, columns or rows
- · Add or remove columns, rows or cells
- · Split or merge cells
- · Delete the table

To select a table

- 1. Press Select .
- 2. Press outside, but near to, a corner of the table and then drag to the opposite corner.



NOTE

Don't start dragging from inside the table. If you do, you select a table cell instead of the table.

Creating basic objects

To select a column

- 1. Press Select .
- 2. Press inside the column's top cell and then drag to the bottom cell.

To select a row

- 1. Press Select .
- 2. Press inside the row's leftmost cell and then drag to the rightmost cell.

To select a cell

- 1. Press Select .
- 2. Press inside the cell.

To select multiple cells

- 1. Press Select .
- 2. Press inside the top and leftmost cell, and then drag to the bottom and rightmost cell.



If you select multiple cells and drag them to a different position on the page, you create a new table consisting of the selected cells and their contents.

Moving tables

Once you have created a table, you can move it on the page.

To move a table

Select the table and then drag it to a different position on the page.

OR

Select all of the table's cells and then drag the cells to a different position on the page.

Changing a table's properties

You can use the Properties tab to change the table's properties, including its transparency, cell colour and line colour.

To change a table's fill

- 1. Select a table, column, row, cell or selection of cells.
- 2. Press the table's, column's, row's or cell's menu arrow and then select **Properties**.
- 3. Press Fill Effects.

4. Select a fill style:

Fill style	Procedure
None (transparent)	Select No fill.
Solid colour	a. Select Solid fill .
	 b. Do one of the following: Select one of the 40 colours in the palette.
	 Press More and then select a colour in the dialogue box. Press the eyedropper and then select a colour on the screen.
Gradient of two	a. Select Gradient fill.
colours	b. For each colour, do one of the following:Select one of the 40 colours in the palette.
	 Press More and then select a colour in the dialogue box.
	 Press the eyedropper and then select a colour on the screen.
	c. Select an option in the Style drop-down list.
Pattern	a. Select Pattern fill.
	b. Select a pattern.
Picture	a. Select Image fill.
	b. Press Browse .
	 Browse to and select the picture that you want to use as a background and then press Open.
	NOTE
	If you insert a large picture, a dialogue box may appear and prompt you to either reduce the picture's file size or retain the picture's file size. For more information, see <i>Setting image optimisation preferences</i> on page 159.
	 d. Select Keep image size to keep the picture's size, regardles of whether the picture is larger or smaller than the object. OR Select Scale image to fit to resize the picture to fit the object.

5. Optionally, drag the **Object transparency** slider to the right to make the table transparent.

To change a table's line style

1. Select a table.



NOTE

You can only change the line style of an entire table, not individual cells, columns or rows.

Creating basic objects

- 2. Press the table's, column's, row's or cell's menu arrow and then select Properties.
- 3. Press Line Style.
- 4. Change the table's line style.

To change a table's text style

- 1. Select a table, column, row, cell or selection of cells.
- 2. Press the table's, column's, row's or cell's menu arrow and then select **Properties**.
- 3. Press Text Style.
- 4. Change the table's text style (see Formatting text on page 40).

Resizing tables, columns or rows

If you want to customise a table, you can resize the table, a column or a row.

To resize a table

- 1. Select the table.
- 2. Press the table's resize handle (the grey circle) and then drag it to increase or reduce the size of the table.

To resize a column

- 1. Press Select .
- 2. Press the vertical border to the right of the column.

A resize pointer appears.

3. Drag the vertical border to resize the column.

To resize a row

- 1. Press Select .
- 2. Press the horizontal border below the row.

A resize pointer appears.

3. Drag the horizontal border to resize the row.

To resize all cells in a table

- 1. Select the table.
- 2. Press the table's menu arrow and then select Adjust size.

Creating basic objects

- 3. Select one of the following options:
 - o Make same height to make all cells in the table the same height.
 - Make same width to make all cells in the table the same width.
 - Make same size to make all cells in the table the same height and width.
 - o Make cells square to make all cells in the table square.

Adding or removing columns, rows or cells

If you want to customise a table, you can add columns or rows.

To add a column

- 1. Select a column.
- 2. Press the column's menu arrow and then select Insert Column.

A new column appears to the right of the current column.

To remove a column

- 1. Select the column.
- 2. Press the column's menu arrow and then select **Delete Column**.

To add a row

- 1. Select a row.
- 2. Press the row's menu arrow and then select Insert Row.

A new row appears below the current row.

To remove a row

- 1. Select the row.
- 2. Press the row's menu arrow and then select **Delete Row**.

To remove a cell

- 1. Select the cell.
- 2. Press the cell's menu arrow and then select **Delete Cells**.

NOTE

- o Removing a cell deletes the contents of the cell.
- You're unable to remove a cell if it provides the only connection between two halves of a table.

Creating basic objects

Splitting or merging table cells

You can add tables to your page and insert objects into the table's cells. If you want to customise a table, you can split or merge cells.

To split a cell

- 1. Select the cell.
- 2. Press the cell's menu arrow and then select Split.
- 3. Select an option to split the cell into multiple rows and/or columns.



If you split a cell that contains content, the content appears in the upper-left-hand cell after the split.

To merge cells

- 1. Select the cells.
- 2. Press the cells' menu arrow and then select Merge Cells.



If you merge cells that contain content, the merged cell contains the contents of the topleft cell. If the top-left cell is empty, the merged cell contains the contents of the next available non-empty cell, moving from left to right, top to bottom.

Deleting tables and the contents of tables

You can delete the contents of a table or the table itself.



You can delete all objects on a page, including tables, by clearing the page (see *Clearing pages* on page 141).

To delete the contents of a table

- 1. Select the cells containing the content that you want to delete.
- 2. Press Delete X.

To delete a table

- 1. Select the table.
- 2. Press the table's menu arrow and then select **Delete**.

Chapter 5

Working with objects

Selecting objects	53
Changing objects' properties	55
Changing the fill	55
Filling digital ink drawings	57
Changing other properties	58
Saving tool settings	58
Positioning objects	58
Moving objects	58
Moving objects to another page	59
Aligning objects	
Rearranging stacked objects	61
Cutting, copying and pasting objects	62

After creating an object, you can select it and work with it as described in this chapter.




NOTE

The tasks described in this chapter are for all objects, not just basic objects.

Selecting objects

Before you can work with an object, you must select it. You can select an individual object, multiple objects or all objects on a page. When you select an object, a selection rectangle appears around it.



Working with objects

The grey circle in the object's lower right-hand corner is a resize handle (see Resizing objects on page 65).

The green circle above the object is a rotation handle (see Rotating objects on page 67).

The downward arrow in the object's upper right-hand corner is a menu arrow. Press the menu arrow to display a menu of commands.



NOTE

Pressing an object's menu arrow gives you access to the same menu as right-clicking the object.

To select an object

- 1. Press Select .
- 2. Press the object that you want to select.

A selection rectangle appears around the object.



NOTE

If you press an object and a lock symbol appears instead of the menu arrow, the object is locked. Depending on the type of lock, you might have to unlock the object before you can manipulate it (see Locking objects on page 103).

To select multiple objects

- 1. Press Select .
- 2. Press the interactive screen and drag until a rectangle surrounds the objects you want to select.

OR

Hold down CTRL and then press the objects you want to select.

A selection rectangle appears around the selected objects.



NOTE

If you draw a rectangle around multiple objects and some of the objects are locked (see Locking objects on page 103), you select only the unlocked objects.

To select all objects on a page

Select Edit > Select All.

A selection rectangle appears around all objects on the page.

NOTE

If some of the objects are locked (see Locking objects on page 103), you select only the unlocked objects.

To select all locked objects on the page

Select Edit > Select All Locked Notes.

A selection rectangle appears around all locked objects on the page.

Changing objects' properties

You can change an object's properties. The properties that you can change depend on the object that you select. You can also select several objects and change their properties at the same time.

Changing the fill

You can change an object's fill by selecting the object and then setting the fill in the Properties tab or by clicking **Fill** , setting the fill and then selecting the object.

To change an object's fill by first selecting the object

- 1. Select the object.
- 3. Press Fill Effects.

4. Select a fill style:

Fill style	Pro	cedure
None (transparent)		Select No fill.
Solid colour	a.	Select Solid fill.
	b.	Do one of the following:
		 Select one of the 40 colours in the palette.
		 Press More and then select a colour in the dialogue box.
		 Press the eyedropper and then select a colour on the screen.
Gradient of two	a.	Select Gradient fill.
colours	b.	For each colour, do one of the following:
		 Select one of the 40 colours in the palette.
		 Press More and then select a colour in the dialogue box.
		 Press the eyedropper and then select a colour on the screen.
	C.	Select an option in the Style drop-down list.
Pattern	a.	Select Pattern fill.
	b.	Select a pattern.
Picture	a.	Select Image fill.
	b.	Press Browse.
	C.	Browse to and select the picture that you want to use as a background and then press Open .
		NOTE
	If you insert a large picture, a dialogue box may appear and prompt you to either reduce the picture's file size or retain the picture's file size. For more information, see <i>Setting image optimisation preferences</i> on page 159.	
	d.	of whether the picture is larger or smaller than the object. OR
		Select Scale image to fit to resize the picture to fit the object.

5. Optionally, drag the **Object transparency** slider to the right to make the object transparent.




You can also change an object's properties using the property selectors on the toolbar.

To change an object's fill by first pressing the Fill button

- 1. Press **Fill** and then select a colour.
- 2. Select the object.
- 3. Repeat step 2 for each object that you want to apply the fill to.

Filling digital ink drawings

In addition to filling shapes, regular polygons and irregular polygons, you can fill areas enclosed by digital ink using the *Fill* button.



NOTES

- To fill an area, you must enclose it with a single digital ink path.
- You're unable to fill an enclosed area if that area is part of a group (see *Grouping objects* on page 68).
- When you fill an enclosed area, the fill becomes a separate object, which you can move away from the original enclosed area. You can fill the enclosed area and move the resulting fill object multiple times.

Working with objects

Changing other properties

In addition to fill, you can change objects' line style and text style.

To change an object's line style

- 1. Select the object.
- 3. Press Line Style.
- 4. Change the object's line style.

To change an object's text style

- 1. Select the object.
- 3. Press **Text Style**.
- 4. Change the object's text style (see Formatting text on page 40).

Saving tool settings

When you select a tool in the toolbar, you can change its default settings using the Properties tab and then save your changes by clicking **Save Tool Properties**.

When you save your changes to a tool's default settings, the tool's button displays those changes:



To restore the default settings, see Customising the toolbar on page 155.

Positioning objects

You can change the position of an object by moving it to another area of the existing page or to another page. You can also align objects and change the order of stacked objects.

Moving objects

You can move objects to another position on the page. You can also flick objects.



You're unable to move an object if it's locked in place (see Locking objects on page 103).

TIP

You can manipulate multiple objects by selecting them and then creating a group (see Grouping objects on page 68).

To move an object or objects

- 1. Select the object or objects.
- 2. Drag the object or objects to a new position on the page.




You can move an object in small increments by pressing the arrow keys on your keyboard.

To move an Adobe Flash® Player compatible file

- 1. Press the coloured bar at the top of the Adobe Flash Player compatible file.
- 2. Drag the file to its new position.

To flick an object

- 1. Select the object.
- 2. Quickly flick your finger in any direction.



Moving objects to another page

You can move objects to another page in a file.

To move an object or objects to another page

- 1. If the Page Sorter isn't visible, press Page Sorter .
- 2. If you don't see the page that you want to move the object to, scroll in the Page Sorter until you see the page's thumbnail.
- 3. Select the object or objects that you want to move.
- 4. Drag the object or objects into the Page Sorter above the thumbnail of the page that you want to move the objects to.

To move an Adobe Flash Player compatible file to another page

- 1. If the Page Sorter isn't visible, press **Page Sorter** .
- 2. If you don't see the page that you want to move the object to, scroll in the Page Sorter until you see the page's thumbnail.
- 3. Press the coloured bar at the top of the Adobe Flash Player compatible file.
- 4. Drag the file into the Page Sorter above the thumbnail of the page that you want to move the object to.

Aligning objects

You can use the Alignment Tools add-on to align and distribute objects on a page. You can align selected objects on the bottom, left, right, top, vertically or horizontally. You can also align stacked objects vertically or horizontally.

If you want, you can display guidelines on a page to assist you in manually aligning objects with other objects, as well as the page's vertical and horizontal centres. You can also set objects to align automatically with these guidelines when you move the objects on a page (see page 58).

To align objects on a page

- 1. Select the objects you want to align (see Selecting objects on page 53).
- 2. Press **Add-ons** don the toolbar to display the Alignment Tools buttons.
- 3. Press an alignment button:

Button	Name	Select this button to:
ш	Align bottom	Align selected objects along their bottom edge.
	Align left	Align selected objects along their left edge.
*	Align middle X	Align selected objects vertically through the middle of the objects.
502	Align middle Y	Align selected objects horizontally through the middle of the objects.
3	Align right	Align selected objects along their right edge.
10	Align top	Align selected objects along their top edge.
	Stack horizontally	Align selected stacked objects horizontally.
	Stack vertically	Align selected stacked objects vertically.

To display guidelines

1. Select View > Alignment.

The Alignment dialogue box appears.

2. Select tickboxes to specify which guidelines you want to display:

Tickbox	Select this tickbox to:
Show guides for active objects	Display a guideline when you move an object into alignment with another object.
Show vertical page centre guide	Display a guideline when you move an object into alignment with the page's vertical centre.
Show horizontal page centre guide	Display a guideline when you move an object into alignment with the page's horizontal centre.
Snap objects to guides	Automatically align objects to guidelines when you move the objects on a page.

- 3. If you want to change the colour of the guidelines, press the coloured bar to the left of Guide colour and then select a colour.
- 4. Press OK.

Rearranging stacked objects

If objects overlap on a page, you can rearrange the order of the stack (that is, you can control which objects appear in front of others).



NOTE

You're unable to move an object in the stack if it's locked in place (see Locking objects on page 103).

To move an object to the front of the stack

- 1. Select the object.
- 2. Press the object's menu arrow and then select Order > Bring to Front.

To move an object to the back of the stack

- 1. Select the object.
- 2. Press the object's menu arrow and then select **Order > Send to Back**.

To move an object one place forward in the stack

- 1. Select the object.
- 2. Press the object's menu arrow and then select **Order > Bring Forward**.

Working with objects

To move an object one place backward in the stack

- 1. Select the object.
- 2. Select the object's menu arrow and then select **Order > Send Backward**.

Cutting, copying and pasting objects

You can cut, copy and paste objects—including text, pictures, straight lines, arcs and shapes—in a .notebook file.

TIPS

- You can paste text from other programs into SMART Notebook software and cut text from SMART Notebook software and paste it into other programs (see *Cutting, copying and* pasting content from other programs on page 81 and *Cutting and pasting text* on page 44).
- You can create an exact copy of an object by cloning it (see Cloning objects on page 64).

To cut and paste an object

- 1. Select the object.
- 2. Press the object's menu arrow and then select Cut.
 - TIE

Alternatively, you can press **Cut** $\stackrel{\checkmark}{N}$ if you added this button to the toolbar (see *Customising the toolbar* on page 155).

- 3. If you want to paste the object onto a different page, display that page.
- 4. Press Paste 違.

To copy and paste an object

- 1. Select the object.
- 2. Press the object's menu arrow and then select Copy.
 - TIP

Alternatively, you can press **Copy** if you added this button to the toolbar (see *Customising the toolbar* on page 155).

- 3. If you want to paste the item onto a different page, display that page.
- 4. Press Paste 違.

Chapter 6

Cropping images with a mask

You can use a mask to crop images. The mask hides the section of the image you crop out instead of deleting it. This enables you to edit the mask if you want to crop a different section of the image. You can also unmask the image to restore the original image.


NOTE

You can crop raster images only. For example, you can crop raster pictures that you insert from the Gallery or from your computer. You're unable to crop other types of objects.

To crop an image with a mask

- 1. Select the image.
- 2. Press the image's menu arrow and then select **Mask**.

A cropping mask appears on the image. Cropped out sections of the image are shaded grey.



- 3. Drag the image until the section of the image that you want to keep appears in the cropping mask.
- 4. Optionally, press one of the cropping mask's eight resize handles (the white circles) and then drag it to increase or reduce the cropping mask's size.
- 5. Press anywhere outside of the image to crop it.

To edit the mask

- 1. Select the image.
- 2. Press the image's menu arrow and then select Edit Mask.

A cropping mask appears on the image. Cropped out sections of the image are shaded grey.

Cropping images with a mask

- 3. Drag the image until the section of the image that you want to keep appears in the cropping mask.
- 4. Optionally, press one of the cropping mask's eight resize handles (the white circles) and then drag it to increase or reduce the cropping mask's size.
- 5. Press anywhere outside of the image to crop it.

To restore the image

- 1. Select the image.
- 2. Press the image's menu arrow and then select **Unmask**.

The original image is restored.

Cloning objects

You can create a duplicate of an object by using the Clone command, or you can create multiple copies of an object using the Infinite Cloner command.



NOTE

You can also copy and paste objects, including text, images, straight lines, arcs and shapes (see Cutting, copying and pasting objects on page 62).

To clone an object

- 1. Select the object.
- 2. Press the object's menu arrow and then select Clone.

A duplicate object appears on the page.

To clone an object using the Infinite Cloner

- 1. Select the object.
- 2. Press the object's menu arrow and then select Infinite Cloner.
- 3. Select the object again.

An infinity symbol appears instead of the object's menu arrow.

- 4. Drag the object to another position on the page.
- 5. Repeat step 4 as many times as you want.
- 6. When you have finished cloning the object, select the original object.
- 7. Press the infinity symbol and then clear the selection of **Infinite Cloner**.

Resizing objects

You can resize objects on a page by using the resize handle or the scale gesture (if your interactive product supports multitouch gestures).



NOTE

You're unable to resize an object if it's locked in place (see Locking objects on page 103).

Using the resize handle

To resize an object

- 1. Select the object.
- 2. Press the object's resize handle (the grey circle) and then drag it to increase or reduce the object's size.



NOTE

To keep the shape's original height-to-width ratio, hold down SHIFT whilst you drag the resize handle.

To resize multiple objects


- 1. Group the objects (see *Grouping objects* on page 68) and then select the group.
 - A selection rectangle appears around the group.
- 2. Press the resize handle in the lower-right-hand corner of the selection rectangle.
- 3. Drag the resize handle to increase or reduce the size of the objects.

Using the scale gesture

To resize an object from its centre


- 1. Select the object.
- 2. Using one finger on each hand, press the screen at opposite ends of the object.

3. Drag your fingers in opposite directions to increase the object's size.



OR

Drag your fingers toward each other to decrease the object's size.



To resize an object from its corner or side

- 1. Select the object.
- 2. Using one finger on each hand, press the screen at the corner or side that you want to resize the object from.
- 3. Drag your fingers in opposite directions to increase the object's size.

OR

Drag your fingers toward each other to decrease the object's size.

To resize multiple objects

- 1. Select the objects.
- 2. Using one finger on each hand, press the screen at opposite ends of one of the objects.
- 3. Drag your fingers in opposite directions to increase the objects' size.

OR

Drag your fingers toward each other to decrease the objects' size.



NOTE

The objects resize from their centres regardless of where you press the screen.

Rotating objects

You can rotate objects on a page by using the rotation handle or the rotate gesture (if your interactive product supports multitouch gestures).

NOTES

- You're unable to rotate an object if it's locked in place (see Locking objects on page 103).
- You're unable to rotate tables.

Using the rotation handle

To rotate an object

- 1. Select the object.
- 2. Press the object's rotation handle (the green circle), and then drag it in the direction you want to rotate the object.

To rotate multiple objects

1. Select the objects.


A selection rectangle appears around each object.

2. Press the rotation handle (the green circle) on any one of the selected objects, and then drag it in the direction you want to rotate the object. When you rotate one object, all other selected objects rotate automatically.

Using the rotate gesture

To rotate an object around its centre

- 1. Select the object.
- 2. Using one finger on each hand, press the screen at opposite ends of the object.
- 3. Move your fingers in a circle around the centre of the object to rotate it.



Cropping images with a mask

To rotate an object around a corner

- 1. Select the object.
- 2. Using one finger on each hand, press the screen in the corner that you want to rotate the object around.
- 3. Move your fingers in a circle around the corner to rotate the object.

To rotate multiple objects

- 1. Select the objects.
- 2. Using one finger on each hand, press the screen at opposite ends of one of the objects.
- 3. Move your fingers in a circle.



NOTE

The objects rotate around their centres regardless of where you press the screen.

Flipping objects

You can flip an object on a page.



NOTE

You're unable to flip an object if it's locked in place (see Locking objects on page 103).

To flip an object

- 1. Select the object.
- Press the object's menu arrow and then select Flip > Up/Down or Flip > Left/Right.

To flip multiple objects

- 1. Select the objects.
- 2. Press the menu arrow on any one of the selected objects and then select Flip > Up/Down or Flip > Left/Right.

Grouping objects

You can create a group of objects, which lets you interact with all grouped items at the same time. Once you have created a group, you can select, move, rotate or resize the group as if it were an individual object. However, if you want to interact with an individual object in a group, you must ungroup the objects first.

Cropping images with a mask

Grouping objects manually

You can group and ungroup objects manually using the menu or the shake gesture.

Using the menu

To group objects

- 1. Select the objects.
- 2. Press the menu arrow of any one of the selected objects and then select **Group > Group**.

To ungroup objects

- 1. Select the group.
- 2. Press the group's menu arrow and then select **Group > Ungroup**.


Using the shake gesture

NOTES

- You're unable to use the shake gesture with a mouse.
- The shake gesture works only when you initially contact your interactive product's surface.

To group objects

Quickly shake your finger over the objects three times.



To ungroup objects

Quickly shake your finger over the group three times.



Grouping objects automatically

If you write or draw multiple lines, SMART Notebook software automatically combines the lines into a single object. For example, if you write the letters of a word, SMART Notebook software combines the individual letters, enabling you to interact with the whole word. If you want to write words on the same line but don't want them combined, leave a large gap between them, use different pens, or briefly put the pen in the pen tray before writing another word (interactive whiteboards only).

If SMART Notebook software combined lines that you want to manipulate individually, ungroup the lines as described above.

Deleting objects

Although you can erase digital ink (see Erasing digital ink on page 34), you're unable to erase some types of objects, including text, shapes, straight lines, arcs and pictures. To remove these types of objects from a page, you must delete them.



NOTE

You're unable to delete an object if it's locked in place (see Locking objects on page 103). To delete a locked object from a page, you must unlock it.

To delete an object

- 1. Select the object.
- 2. Press the object's menu arrow and then select **Delete**.

Chapter 7

Inserting, organising and sharing content

You can insert pictures, multimedia files and other content into your .notebook files from a variety of sources. These sources include the Gallery, the SMART Exchange™ website and the Internet.

After inserting your content, you can organise it using the Gallery and share it with other teachers using the Gallery or the SMART Exchange website.

Inserting content from the Gallery

The Gallery is a tab in the SMART Notebook software user interface where you can browse or search for content and then add that content to your .notebook files.

The Gallery contains Lesson Activity Examples, which includes Activity Builder examples (see *Creating a matching lesson activity* on page 110), interactive techniques and 3D models to aid you in creating lesson activities.

When your system administrator installs SMART Notebook software, he or she can install the following additional items:

- Gallery Essentials is a collection of thousands of pictures, multimedia objects and more, organised into subject-specific categories.
- Lesson Activity Toolkit is a collection of customisable tools and templates that you can use
 to create professional-looking and interactive lessons. The toolkit helps you create engaging
 content like word games, quizzes and sorting activities. It also offers Adobe Flash Player
 compatible files like hide-and-reveal and drag-and-drop.

Inserting, organising and sharing content

The Gallery is divided into two sections. The top section of the Gallery is the category list. When you select a category or subcategory in the list, its contents appear in the bottom section of the Gallery.



You can change the size of the category list and content list by pressing the boundary between them and then dragging it up or down.

You can browse the category list to view the contents of each category. Thumbnails in the categories provide preview images of the content.

- In Pictures, pictures appear as thumbnails.
- In Interactive and Multimedia, video objects appear as a single frame from the videos, sound objects appear with a speaker icon in the lower left-hand corner, and Adobe Flash Player compatible files appear as an Adobe Flash icon or thumbnail of the content with a small Adobe Flash icon in the upper left-hand corner.
- In 3D Objects, 3D models appear as thumbnails.
- In Notebook Files and Pages, files appear as binders and pages appear with a folded upper right-hand corner.
- In Backgrounds and Themes, backgrounds appear as pages with a folded lower right-hand corner and themes appear as thumbnails.

You can search for a Gallery item using the keyword search.

After browsing or searching for a Gallery item, you can add it to your .notebook file.

To browse the Gallery

- 1. If the Gallery isn't visible, press Gallery ...
- 2. Press a category's plus sign to view its subcategories.



NOTE

You can close a category by pressing the category's minus sign.

3. Select a category or subcategory to display its contents.

To search the Gallery

- 1. If the Gallery isn't visible, press **Gallery** .
- 2. Type a keyword into the *Type search terms here* box and then press **Search** *E*. The Gallery displays all content containing the keyword.

Inserting, organising and sharing content

To add a Gallery item to your .notebook file

- 1. If the Gallery isn't visible, press **Gallery** .
- 2. Browse or search for the Gallery item that you want to add.
- 3. Double-click the Gallery item's thumbnail.
 - If you add a picture, Adobe Flash Player compatible file, video file or sound file, it appears on the current page.
 - If you add a background, it replaces the page's existing background (see Applying page backgrounds and themes on page 106).
 - If you add a page from a .notebook file, SMART Notebook software inserts it before the current page.
 - If you add a .notebook file, SMART Notebook software inserts the file's pages before the current page.

Chapter 8

Inserting content from GeoGebra

GeoGebra is a free interactive mathematics software for all levels of education. When you insert the GeoGebra widget in SMART Notebook software, you can explore geometry, algebra, tables, graphing, statistics and calculus with your students.

You can also search for worksheets from GeoGebraTube using the keyword search. After searching for a worksheet, you can add it to your .notebook file. GeoGebraTube (geogebratube.org) contains thousands of worksheets created and shared by other teachers.



NOTE

For more information on how to use GeoGebra software, go to the GeoGebra Wiki (wiki.geogebra.org).

To access the GeoGebra widget

Press Add-ons deand then press GeoGebra.

- To insert the GeoGebra widget
 - 1. If the GeoGebra widget isn't visible, press Add-ons de and then press GeoGebra.
 - 2. Select Insert GeoGebra Widget.
- To search GeoGebraTube
 - 1. If the GeoGebra widget isn't visible, press Add-ons de and then press GeoGebra.
 - 2. Type a keyword into the Search in Free Materials box and then press Search. The GeoGebra widget displays thumbnail images of worksheets containing the keyword.
- To add a GeoGebraTube worksheet to your .notebook file
 - 1. If the GeoGebra widget isn't visible, press Add-ons de and then press GeoGebra.
 - 2. Search for the GeoGebraTube worksheet that you want to add.

3. Press the worksheet's thumbnail and then select Insert GeoGebra Widget.

The worksheet appears on the current page.



For more information on a worksheet, press the thumbnail's title to go to the worksheet's download page in GeoGebraTube.

Inserting content from the SMART Exchange website

The SMART Exchange website (exchange.smarttech.com) includes thousands of lesson plans, question sets, widgets and other content that you can download and then open in SMART Notebook software.



NOTE

You can also share your lesson plans with other teachers through the SMART Exchange website. For more information, see Sharing content using the SMART Exchange website on page 95.

To insert content from the SMART Exchange website

1. Press **SMART Exchange SMART**

The SMART Exchange website opens in your web browser.

2. If you're new to the SMART Exchange website, press Join for free and then follow the onscreen instructions to create an account.

OR

If you have an account, press Sign In and then follow the on-screen instructions to log on to the SMART Exchange website with your account.

- 3. Search or browse for content and then download it to your computer.
- 4. Import content into the Gallery (see Sharing content with other teachers on page 93).

Inserting content from other sources

If you or other teachers in your school have created content outside of SMART Notebook software, you can include this content in your .notebook files. Specifically, you can do the following:

- Insert pictures, Adobe Flash Player compatible files and video files, and sound files
- Cut or copy and then paste content from other programs

Inserting content from GeoGebra

· Import content from other programs

Inserting pictures

You can insert pictures into pages from files, a scanner or a SMART Document Camera.



NOTE

You can also insert pictures from the Gallery tab. For more information, see Inserting content from the Gallery on page 71.

Once you have inserted a picture, you can define a transparent area in it.

Inserting pictures from files

You can insert a picture into a page.

SMART Notebook software supports BMP, GIF, JPEG, PNG, TIFF and WMF formats.

To insert a picture from a file

1. Select Insert > Picture.

The Insert Picture File dialogue box appears.

2. Browse to and select the picture that you want to insert.



To select more than one picture, hold down CTRL and then select the pictures.

3. Press Open.

The picture appears in the upper-left-hand corner of the page.

Inserting pictures from a scanner

If a scanner is connected to your computer, you can insert pictures from the scanner into a page.



NOTE

You must install your scanner's driver and software on your computer before inserting pictures from the scanner into SMART Notebook software.

To insert a picture from a scanner

1. Select Insert > Picture From Scanner.

The Insert Scanned Picture dialogue box appears.

2. Select a scanner from the list.

Inserting content from GeoGebra

- 3. Press Scan.
- 4. Follow the instructions included with your scanner to scan your picture.

Inserting pictures from a SMART Document Camera

You can insert pictures from a SMART Document Camera into a page.

To insert a picture from a SMART Document Camera

1. Select Insert > Picture From SMART Document Camera.

The SMART Document Camera window appears on the page.

2. Insert a picture following the instructions in the Help.

Working with pictures

When you insert a picture in a .notebook file, the picture becomes an object in the file. Therefore, you can move, resize, rotate and make other changes to the picture like any other object.

For information on how to work with objects, including pictures, in .notebook files, see Working with objects on page 53.

Creating transparent areas in a picture

You can create transparent areas in a picture that you insert into a page. This is useful for removing the picture's background. You can make any colour in the picture transparent.



NOTE

You can reduce the size of a large picture when you insert it in a file (see Setting image optimisation preferences on page 159). If you later create a transparent area in the picture, the picture is no longer optimised.

To create a transparent area in a picture

- 1. Select the picture.
- 2. Press the picture's menu arrow and then select **Set Picture Transparency**.

The Picture Transparency dialogue box appears.

3. Press any areas in the picture that you want to make transparent.



NOTE

Pressing an area makes only that area transparent, even if the picture includes that same colour in other areas.

4. Press OK.

Inserting multimedia files

You can insert multimedia files, including Adobe Flash Player compatible files, video files and sound files, into pages.

NOTE

You can also insert multimedia files from the Gallery tab. For more information, see *Inserting* content from the Gallery on page 71.

Inserting Adobe Flash Player compatible files

You can insert Adobe Flash Player compatible files into a page.

Once you have inserted an Adobe Flash Player compatible file into a page, or display a page that already contains an Adobe Flash Player compatible file, the file plays immediately. You can control the playback of the file. If the file has buttons, you can press them on your interactive product. If the file doesn't have buttons, you can use the options in the file's menu arrow.

NOTES

- Adobe Flash Player compatible files on a page must be self-extracting. You're unable to use Adobe Flash Player compatible files that load or rely on other Adobe Flash Player compatible files.
- You're unable to drag an Adobe Flash Player compatible file from an Internet browser into a page.
- If Adobe Flash Player isn't installed on your computer, SMART Notebook software notifies you when you insert an Adobe Flash Player compatible file into a page.
- You can install Adobe Flash Player by visiting adobe.com, but you must use Internet Explorer® Internet browser to install it. If you use another browser, Adobe Flash Player compatible files don't work in SMART Notebook software.
- To write on top of an Adobe Flash Player compatible file with a handwriting recognition component, start writing outside the file and continue to write over the file. This enables SMART Notebook software to recognise the digital ink as a separate object from the Adobe Flash Player compatible file.

To insert an Adobe Flash Player compatible file

1. Select Insert > Adobe Flash Player Compatible File.

The Insert Flash File dialogue box appears.

- 2. Browse to and select the Adobe Flash Player compatible file that you want to insert into the page.
- 3. Press Open.

The Adobe Flash Player compatible file appears in the upper left-hand corner of the page.

To control an Adobe Flash Player compatible file

- 1. Select the Adobe Flash Player compatible file.
- 2. Control the file by doing any of the following:
 - To play the file, press the file's menu arrow and then select Flash > Play.
 - To play the file from the beginning, press the file's menu arrow and then select Flash > Rewind.
 - To advance the file slightly and pause playback, press the file's menu arrow and then select Flash > Step Forward.
 - To rewind the file slightly and pause playback, press the file's menu arrow and then select Flash > Step Back.
 - To play the file continuously, press the file's menu arrow and then select Flash > Loop.
 - To stop playing the file continuously, press the file's menu arrow and then clear the selection of Flash > Loop.

Inserting Adobe Flash Player compatible video files

You can insert Adobe Flash Player compatible video files into a page.



NOTE

SMART Notebook software supports the Adobe Flash Player compatible video file (FLV) format. If you want SMART Notebook software to support other file types, you can install additional encoders (see Installing encoders for additional formats on the next page).

To insert an Adobe Flash Player compatible video file

1. Select Insert > Video.

The Insert Video File dialogue box appears.

- 2. Browse to and select the Adobe Flash Player compatible video file that you want to insert into the page.
- 3. Press Open.

Inserting sound files

You can attach a sound file to any object (except Adobe Flash Player compatible objects) in a .notebook file. For more information, see Adding sounds to objects on page 102.

Working with multimedia files

When you insert a multimedia file in a .notebook file, the multimedia file becomes an object in the file. Therefore, you can move, resize, rotate and make other changes to the multimedia file like any other object.

Inserting content from GeoGebra

For information on how to work with objects, including multimedia files, in .notebook files, see Working with objects on page 53.

Installing encoders for additional formats

SMART Notebook software supports the FLV and MP3 formats. If you want SMART Notebook software to support other video and audio formats, you can install the following encoder. If you install this encoder, SMART Notebook software automatically detects it and supports its video and audio formats.

Encoder	Video formats	Audio formats	Link
MediaCoder Full Pack 0.3.9	• ASF	 AIF and AIFF 	mediacoderhq.com/dlfull.htm
	AVI	WAV	
	MOV		
	MPEG and MPGWMV		



NOTE

SMART Technologies ULC provides links to these programs as a courtesy and makes no representations or warranties regarding the programs or any information related thereto. Any questions, complaints or claims regarding the programs must be directed to the appropriate software vendor.

Inserting content from other programs

If you have content in other programs that you want to use in your .notebook files, you can move this content to SMART Notebook software by doing one of the following:

- · Cutting or copying and then pasting the content
- · Importing the content

Cutting, copying and pasting content from other programs

You can cut or copy, and then paste content from other programs into SMART Notebook software.

To cut content from another program

- 1. In the other program, select the content you want to cut and then select Edit > Cut.
- 2. In SMART Notebook software, press Paste ...

To copy content from another program

- In the other program, select the content you want to copy and then select Edit > Copy.
- 2. In SMART Notebook software, press Paste ...

Importing content using SMART Notebook Print Capture

When you install SMART Notebook software on a computer with Windows XP operating system, you also install SMART Notebook Print Capture. SMART Notebook Print Capture works like any other printer driver, except it captures output in a .notebook file, instead of printing it on paper. Each page of an imported file appears as an object on its own page, with its original formatting and page breaks preserved.



NOTE

If you install SMART Notebook software on a computer with Windows 7 or Windows 8 operating system, you can import content using SMART Notebook Document Writer (see Importing content using SMART Notebook Document Writer on the next page).

To use SMART Notebook Print Capture

- 1. In the source file that you want to export to a .notebook file, select **File > Print**.
 - The *Print* dialogue box appears.
- 2. Select SMART Notebook Print Capture in the list of printers.
- 3. Optionally, change the page orientation and graphics resolution (see *To change the page* orientation and graphics resolution below).
- 4. Specify a page range and then press **OK** or **Print**.

If an existing .notebook file isn't open, a new .notebook file opens. Each page of the source file appears on a separate page.

OR

If an existing .notebook file is open, each page of the source file appears in the .notebook file after the current page.



NOTE

This process can take several minutes.

To change the page orientation and graphics resolution

1. Press the **Properties** or **Preferences** button.

The SMART Notebook Print Capture Properties dialogue box appears.

2. Select Portrait or Landscape.

Inserting content from GeoGebra

3. Select a default resolution in the Resolution drop-down list.

OR

Select CUSTOM Resolution in the Resolution drop-down list and then type numbers in the Horizontal Resolution and Vertical Resolution boxes.



TIPS

- Use the same value in both boxes to prevent image distortion.
- o The higher the resolution, the larger the image.
- o Don't use the **Draft**, **Low** or **Medium** options because they might not scale the image proportionally.

4. Press OK.

Importing content using SMART Notebook Document Writer

When you install SMART Notebook software on a computer with Windows 7 or Windows 8 operating system, you also install SMART Notebook Document Writer. SMART Notebook Document Writer works like any other printer driver, except it captures output in a .notebook file, instead of printing it on paper.



NOTE

If you install SMART Notebook software on a computer with Windows XP operating system, you can import content using SMART Notebook Print Capture (see Importing content using SMART Notebook Print Capture on the previous page).

To use SMART Notebook Document Writer

- 1. In the source file that you want to export to a .notebook file, select **File > Print**. The Print dialogue box appears.
- 2. Select **SMART Notebook Document Writer** in the list of printers.
- 3. Optionally, change the page orientation (see To change the page orientation on the next page).
- 4. Specify a page range and then press OK or Print.

A dialogue box appears.

Inserting content from GeoGebra

5. Select **SMART Notebook pages with images** to import the content of the file as pictures.

OR

Select SMART Notebook page with editable objects to import the content of the file as editable objects.



NOTE

If you choose to import the content as editable objects, some objects may not display correctly. You can import the content as pictures.

6. Press OK.

A new .notebook file opens. Each page of the source file appears on a separate page.

To change the page orientation

1. Press Properties or Preferences.

The Printing Preferences dialogue box appears.

- 2. Select **Landscape** or **Portrait** in the *Orientation* drop-down list.
- 3. Press OK.

Importing PowerPoint files

You can import content into a .notebook file from a variety of sources, including PowerPoint files.



NOTE

SMART Notebook software doesn't import some gradient, pattern and picture effects. These effects may appear incorrectly in .notebook files as a result.



You can also export .notebook files to PowerPoint (see Exporting files on page 15).

To import a PowerPoint file

Select File > Import.

The Open dialogue box appears.

- 2. Select All PowerPoint Files (*.ppt;*.pptx) in the Files of type drop-down list.
- 3. Browse to and select the PowerPoint file that you want to import.
- 4. Press Open.

SMART Notebook software adds the contents of the PowerPoint file to a .notebook file.

Inserting content from GeoGebra

Importing files from other interactive whiteboard programs

You can import content into .notebook files from a variety of sources, including other interactive whiteboard programs.

If the other interactive whiteboard programs support the Interactive Whiteboard Common File Format (CFF), you can export a CFF file from those programs and then import that CFF file into SMART Notebook software.

Otherwise, you can attempt to import the other interactive whiteboard programs' native file formats.



NOTE

You can also export CFF files (see Exporting files on page 15).

To import CFF files

Select File > Import.

The *Open* dialogue box appears.

- 2. Select All Common File Format Files (*.iwb) in the Files of type drop-down list.
- 3. Browse to and select the file that you want to import.
- 4. Press Open.

The file opens.

To import other files

Press Open File

The *Open* dialogue box appears.

- 2. Select All Files (*.*) in the Files of type drop-down list.
- 3. Browse to and select the file that you want to import.
- 4. Press Open.

If you import a file that SMART Notebook software supports, the file opens.

OR

If you import a file that SMART Notebook software doesn't support, SMART Notebook software adds it to the Attachments tab. You can open these attached files using third-party software, but you're not able to add them to a page.


Inserting equations with the Maths Editor

You can use the Maths Editor to insert a handwritten equation onto a page in a more readable format. The Maths Editor recognises your handwriting and automatically converts it to a typeset format. You can also add the recognised equation to a GeoGebra worksheet if the equation is in a supported graph format.

To insert an equation onto the page

- 1. Press **Add-ons** \clubsuit and then select **Insert Equation** Σ **!**. The Maths Editor appears.
- 2. Select a pen tool (see Writing or drawing digital ink on page 32).
- 3. Write a maths equation on the graph paper section of the editor.

The handwritten equation converts to a typed equation, which appears below the graph paper section. Accept and reject icons appear beside the recognised equation.



4. Press of to accept the recognised equation.

The typed equation appears on the page.

OR

Press 8 to reject the recognised equation and close the Maths Editor.

To edit the recognised equation

- Double-click the recognised equation on the page.
 - The handwritten equation appears on the Maths Editor.
- 2. Select a pen tool (see Writing or drawing digital ink on page 32).

Inserting content from GeoGebra

3. Edit the handwritten equation.

The handwritten equation converts to a typed equation, which appears below the graph paper section. Accept and reject icons appear beside the recognised equation.

Press of to accept the recognised equation.

The equation updates with your edits.

OR


Press to reject the typed equation and close the Maths Editor.

The equation doesn't update.

To add the recognised equation to a GeoGebra worksheet

- 1. Insert a GeoGebra worksheet on the page (see Inserting content from GeoGebra on page 75).
- 2. Drag the equation from the page to the GeoGebra widget.

The equation is automatically graphed in the worksheet.



Inserting Internet browsers

You can insert an Internet browser into a .notebook page. In the Internet browser, you can browse to and display webpages. You can modify the Internet browser like any other object in SMART Notebook software (see Working with objects on page 53).



NOTE

When you resize an Internet browser, the Internet browser's content is rescaled automatically so that you always see the entire webpage that you are viewing.

Inserting an Internet browser

To insert an Internet browser

1. Select Insert > Internet Browser.

An Internet browser appears.

2. Double-click the address bar, type the address of the webpage that you want to browse to and then press Go .



If there's no keyboard connected to your computer, click SMART Keyboard E to display an on-screen keyboard.

3. Interact with the website using the buttons in the Internet browser toolbar:

Button	Command	Action
4	Back	Display the previous webpage.
→	Forward	Display the next webpage.
Q	Return to Pinned Page	Open the pinned webpage.
Ø	Pin Page	Pin the current webpage. When you first open the .notebook file, the pinned webpage appears in the Internet browser. You can return to the pinned page at any time by pressing Return to Pinned Page .
C	Reload	Reload the current webpage.
\$	Move Toolbar	Change the position of the Internet browser toolbar.

Configuring proxy servers

Internet browsers in SMART Notebook software work with any proxy server that adheres to the RFC 2068 HTTP standard. If your system administrator installed SMART Notebook software behind a proxy server, he or she must create access policy rules for inbound and outbound traffic on that proxy server. Your system administrator can further enhance network security by enabling authentication, such as basic or NT LAN Manager (NTLM) authentication.



NOTE

Although proxy servers protect internal networks from intruders, they unavoidably introduce network latency.

Attaching files and webpages

You can attach copies of files, shortcuts to files and links to webpages using the Attachments tab.

Attaching files or webpages enables you to find and open these items easily while presenting a .notebook file.

NOTES

- You can also link a file or webpage to an object on a page (see Adding links to objects on page 100).
- As an alternative to attaching a link to a webpage, you can also insert an Internet browser in your .notebook file (see *Inserting Internet browsers* on page 87).

To attach a copy of a file

- 2. Press Insert at the bottom of the Attachments tab and then select Insert Copy of File. The Insert Copy of File dialogue box appears.
- 3. Browse to and select the file that you want to attach.
- 4. Press Open.

The file's name and size appear in the Attachments tab.



NOTE

When you attach a file, the size of the .notebook file increases. Although SMART Notebook software compresses files to conserve space, SMART Notebook software can compress some file types more than others.

To attach a shortcut to a file

- 2. Press Insert at the bottom of the Attachments tab and then select Insert Shortcut to File. The Insert File Shortcut dialogue box appears.
- 3. Browse to and select the file that you want to attach.

4. Press Open.

The file name and Shortcut appear in the Attachments tab.



NOTES

- SMART Notebook software doesn't export shortcuts. If you want to export file attachments, attach a copy of your file, not a file shortcut.
- o Make sure that the file is accessible on the computer that you will use during the

To attach a link to a webpage

- 2. Press **Insert** at the bottom of the *Attachments* tab and then select **Insert Hyperlink**.

The Insert Hyperlink dialogue box appears.

- 3. Type the webpage's address in the *Hyperlink* box.
- 4. Type a name for the link in the *Display name* box.
- 5. Press OK.

The display name and *URL* appear in the *Attachments* tab.

To open a file or webpage from the Attachments tab

The Attachments tab lists all attachments in the open file.

- If an attached item is a copy of a file, the file's size appears in the Size column.
- o If an attached item is a shortcut to a file, Shortcut appears in the Size column.
- o If an attached item is a link to a webpage, URL appears in the Size column.
- 2. To open a file, double-click the file name or shortcut.

OR

To open a webpage, double-click the link.

Organising and sharing content using the Gallery

The Gallery is a tab in the SMART Notebook software user interface where you can browse or search for content and then add that content to your .notebook files. The Gallery consists of a set of categories, one of which is the My Content category.

Inserting content from GeoGebra

If you find you use the same content across multiple .notebook files, you can add this content to the My Content category. You can share content from the My Content category with other teachers in your school by importing or exporting Gallery collection files. You can also connect to a Team Content category containing content that you and other teachers in your school contribute to.

After adding your content to the Gallery, you can insert it into .notebook files as described in *Inserting content from the Gallery* on page 71.

Adding content to the Gallery

You can add SMART Notebook software objects and pages as well as supported files to the My Content category in the Gallery.

To add an object to the Gallery

- 1. If the Gallery isn't visible, press **Gallery** ■.
- 2. Select the object that you want to add to the Gallery.
- 3. Drag the object from the page to the Gallery's *My Content* category or one of its subcategories.

NOTES NOTES

- You're unable to drag an object if it's locked in place (see Locking objects on page 103).
- If you want to change a Gallery item's name, select the item, press its menu arrow and then select **Rename**.

To add a page to the Gallery

- 1. Create and modify objects on the page until the page appears exactly as you want it to.
- 2. Select File > Export Page as Gallery Item.

The Save Page as Gallery Item dialogue box appears.

- 3. Browse to the folder in which you want to save the page.
- 4. Type a name for the page in the File name box.
- 5. Press Save.
- 6. If the Gallery isn't visible, press **Gallery** ■.

Inserting content from GeoGebra

7. Select My Content (or one of its subcategories) in the Gallery's category list, press its menu arrow and then select Add to My Content.

The Add to My Content dialogue box appears.

- 8. Browse to and select the item that you saved in step 5.
- 9. Press Open.

To add a supported file to the Gallery

- 1. If the Gallery isn't visible, press Gallery ...
- 2. Select My Content (or one of its subcategories) in the Gallery's category list, press its menu arrow and then select Add to My Content.

The Add to My Content dialogue box appears.

- 3. Browse to and select the item that you want to add to the Gallery.
- 4. Press Open.



NOTE

By default, SMART Notebook software names the new Gallery item based on the original file name. If you want to change the item's name, select the Gallery item's thumbnail, press its menu arrow and then select Rename.

Organising content in the Gallery

As you add objects, pages and supported files to the My Content category in the Gallery, you may want to reorganise the category's structure. You can create subcategories and move Gallery items between subcategories.

To create a subcategory

- 1. If the Gallery isn't visible, press **Gallery** .
- 2. Select My Content (or one of its subcategories) in the Gallery's category list, press its menu arrow and then select New Folder.

A new subcategory appears.

3. Type a name for the new subcategory and then press ENTER.

To rename a subcategory

- 1. If the Gallery isn't visible, press **Gallery** ...
- 2. Select My Content in the Gallery's category list and then browse to the subcategory that you want to rename.
- 3. Select the subcategory, press its menu arrow and then select **Rename**.
- 4. Type a new name for the subcategory and then press ENTER.

To move a Gallery item to a different subcategory

- 1. If the Gallery isn't visible, press **Gallery** ...
- 2. Browse to the category that contains the Gallery item that you want to move.

The Gallery displays the contents of the category.

3. Drag the item to another subcategory.

Sharing content with other teachers

Importing and exporting collection files is an ideal way to share custom categories with other teachers and to use categories that other teachers have created. You can use collection files to add items to the My Content category in the Gallery. Once you have imported a collection file, all of its items appear in The Gallery as a new subcategory.

To import a collection file from another teacher

- 1. If the Gallery isn't visible, press **Gallery** .
- 2. Select My Content (or one of its subcategories) in the Gallery's category list, press its menu arrow and then select Add to My Content.

The Add to My Content dialogue box appears.

3. Browse to the folder that contains the collection file that you want to import.



NOTE

A collection file has a .gallery extension.

4. Select the collection file and then press Open.

The collection appears as a new subcategory.

To export a collection file to share with other teachers

1. Select the category that contains the items you want to save in a collection.

NOTE

SMART Notebook software exports the selected category but doesn't export any of its subcategories.

2. Press the category's menu arrow and then select **Export as Collection File**.

The Save As dialogue box appears.

- 3. Browse to the folder where you want to save the collection file.
- 4. Type a name for the file in the File name box.
- 5. Press Save.

Connecting to Team Content categories

The Team Content categories feature enables you to connect to Gallery content in a shared location on your school's network. Multiple teachers can connect to the same folder. SMART Notebook software automatically updates your changes for all other teachers.



NOTE

Your access permissions for the Team Content category are the same as your folder access permissions on your school's network. If you have full access to a folder on the network, you can add or remove items in that folder's Team Content category. However, if you have readonly access to the folder, you can copy items from the Team Content category, but you're unable to add, edit or remove items.

To connect to a Team Content category

- 1. If the Gallery isn't visible, press **Gallery** ...
- 2. Press Show additional Gallery actions 2 and then select Connect to Team Content. The Browse For Folder dialogue box appears.
- 3. Browse to and select the folder containing the Team Content category you want to connect to and then press **OK**.

The Team Content category appears in the Gallery.

To contribute to a Team Content category

Add content to a Team Content category as you do to the My Content category (see Adding content to the Gallery on page 91).

Sharing content using the SMART Exchange website

In addition to sharing your content with other teachers in your school (see Sharing content with other teachers on page 93), you can share .notebook files with teachers from around the world using the SMART Exchange website (exchange.smarttech.com).

To share a .notebook file on the SMART Exchange website

- 1. Open the .notebook file that you want to share.
- 2. Select File > Share on SMART Exchange.

A dialogue box appears.

3. If you're new to the SMART Exchange website, press Not a member yet and then follow the on-screen instructions to create an account.

OR

If you have an account, type your email address in the Email Address box and your password in the Password box and then press Sign In.

TIPS

- o If you have forgottenyour password, click Forgot your password and then follow the on-screen instructions to reset it.
- o If you don't want to log on to the SMART Exchange website each time you share content, select the Keep me signed in tickbox.
- Enter the appropriate information:

Control	Instructions	
Enter resource details Type a title for the .notebook file.		
Description	Type a description of the .notebook file.	
Subject(s)	Select the subjects that the .notebook file is applicable to.	
Grade(s)	Select the grades that the .notebook file is applicable to.	
Search terms	Type words or phrases that other SMART Exchange users are likely enter to search for the .notebook file. Separate the words or phrases with commas.	

- 5. Read the sharing agreement.
- 6. If you accept the sharing agreement, press Agree and Submit.

Chapter 9

Creating lesson activities

Using advanced object features	98
Creating custom Creative pen styles	98
Adding links to objects	100
Adding sounds to objects	102
Animating objects	103
Locking objects	103
Using advanced page features	104
Displaying student page borders	105
Recording pages	105
Applying page backgrounds and themes	106
Applying backgrounds using the Properties tab	106
Applying backgrounds and themes using the Gallery	108
Creating themes	109
Creating example lesson activities	109
Creating a matching lesson activity	110
Creating a hide-and-show lesson activity	111
Creating a reveal lesson activity	113
Creating other types of lesson activities	115
Accessing XC Collaboration	115
=	

Using SMART Notebook software, you can not only present information to students but also engage them in interactive lesson activities.

You can create lesson activities by inserting objects such as shapes, pictures and tables, and using features such as the Activity Builder and scaling gesture.

This section documents the advanced features that you can use to create lesson activities and shows you how to create a set of example lesson activities. You can use these example lesson activities or develop your own. You can also use resources available to you in the Gallery and SMART Exchange website.

Using advanced object features


You can use the following advanced object features when creating lesson activities:

- · Custom creative pen styles
- Object links
- · Object sounds
- Object animation

You can also lock any objects that you don't want moved or otherwise modified during the presentation of a lesson activity.

Creating custom Creative pen styles


SMART Notebook software includes eight Creative pen styles (see *Writing or drawing digital ink* on page 32). In addition to these styles, you can create your own styles using pictures or objects on the currently selected page.



To create a custom Creative pen using a picture

1. Press Pens W.

The Pens tool buttons appear.



- 2. Press Pen Types and then select Creative Pen.
- 3. Select a line type.
- 5. Press Line Style.
- 6. Select Use a custom stamp image.

Creating lesson activities

7. Click Browse.

The Insert Image File dialogue box appears.

- 8. Browse to and select the picture you want to use for the Creative pen style.
- 9. Press Open.
- 10. Write or draw digital ink on the page.




- To resume using the default line type, select **Use the default pattern**.
- o If you want to save your custom Creative pen style for future use, press Save Tool Properties. You can later reset the Creative pen style (see Customising the toolbar on page 155).

To create a custom Creative pen using an object

1. Press Pens W.

The Pens tool buttons appear.



- 2. Press Pen Types and then select Creative Pen.
- 4. Press Line Style.
- 5. Select Use a custom stamp image.
- 6. Press Select object and then select an object on the page.
- 7. Write or draw digital ink on the page.



- To resume using the default line type, select **Use the default pattern**.
- o If you want to save your custom Creative pen style for future use, press Save Tool Properties. You can later reset the Creative pen style (see Customising the toolbar on page 155).

Creating lesson activities

Adding links to objects

You can link any object on a page to a webpage, another page in the file, a file on your computer or an attachment. An attachment is a copy of a file, a shortcut to a file or a link to a webpage that you add to the Attachments tab.



NOTE

You can display animated link indicators around all links on a page (see Displaying links on page 124).

To add a link to a webpage

- 1. Select the object.
- 2. Press the object's menu arrow and then select Link.

The Insert Link dialogue box appears.

- 3. Press **Webpage** and then type the web address in the *Address* box.
- 4. If you want to open the link by pressing an icon, select Corner icon.

If you want to open the link by pressing anywhere in the object, select Object.

5. Press **OK**.

If you selected **Corner icon**, the lower left corner of the object.

To add a link to another page in the file

- 1. Select the object.
- 2. Press the object's menu arrow and then select Link.

The *Insert Link* dialogue box appears.

- 3. Press Page in this File and then select an option in the Select a page area.
- 4. If you want to open the link by pressing an icon, select Corner icon.

If you want to open the link by pressing anywhere in the object, select Object.

5. Press **OK**.

If you selected **Corner icon**, the icon appears in the lower left corner of the object.

To add a link to a file on your computer

- 1. Select the object.
- 2. Press the object's menu arrow and then select Link.

The Insert Link dialogue box appears.

- 3. Press File on this Computer and then type the file's location and name in the File box.
- 4. If you want to attach a copy of the file, select Copy of file.

OR

If you want to insert a shortcut to the file, select Shortcut to file.

5. If you want to open the link by pressing an icon, select **Corner icon**.

OR

If you want to open the link by pressing anywhere in the object, select **Object**.

6. Press **OK**.

If you selected **Corner icon**, the icon appears in the lower left corner of the object.

To add a link to an attachment

- 1. Select the object.
- 2. Press the object's menu arrow and then select **Link**.

The *Insert Link* dialogue box appears.

- 3. Press **Current Attachments** and then select the attachment in the list.
- 4. If you want to open the link by pressing an icon, select Corner icon.

OR

If you want to open the link by pressing anywhere in the object, select Object.

5. Press **OK**.

If you selected **Corner icon**, the sicon appears in the lower left corner of the object.

To remove a link

- 1. Select the object.
- 2. Press the object's menu arrow and then select Link.

The Insert Link dialogue box appears.

3. Press Remove Link.

Adding sounds to objects

You can add a sound to any object (except Adobe Flash Player compatible files and widgets) by attaching a sound file or recording a sound using a computer microphone. You can play the sound during the lesson by pressing an icon in the corner of the object or the object itself.

NOTE

SMART Notebook software supports the MP3 audio format. If you want SMART Notebook software to support other file types, you can install additional encoders (see Installing encoders for additional formats on page 81).

To add a sound file to an object

- 1. Select the object.
- 2. Press the object's menu arrow and then select Sound.

The Insert Sound dialogue box appears.

3. Press Browse.

The Insert File dialogue box appears.

- 4. Browse to and select the sound file and then press **Open**.
- 5. Select Corner Icon if you want to play the sound file when you press an icon in the object's lower left-hand corner.

OR

Select **Object** if you want to play the sound file when you press anywhere on the object.

6. Press Attach Sound.

To add a recorded sound to an object

- 1. Connect a microphone to your computer and turn it on.
- 2. Select the object.
- 3. Press the object's menu arrow and then select Sound.

The Insert Sound dialogue box appears.

- 4. Click Start Recording.
- 5. Record the sound using the microphone.



☑ IMPORTANT

SMART Notebook software stops recording after one minute. Therefore, ensure that the sound is no more than one minute long.

6. Click Stop Recording.

Creating lesson activities

- 7. Type a name for the sound in the Recording name box.
- 8. Optionally, click **Preview Recording** to hear the sound before adding it to the object.
- 9. Select **Corner Icon** if you want to play the sound file when you press an icon in the object's lower left-hand corner.

OR

Select **Object** if you want to play the sound file when you press anywhere on the object.

10. Press Attach Recording.

To remove a sound from an object

- 1. Select the object.
- 2. Press the object's menu arrow and then select **Sound**.

The Insert Sound dialogue box appears.

3. Press Remove Sound.

Animating objects

You can animate an object to fly onto a page from the side, spin, fade in, shrink and more. You can set the animation to start when you open a page or when you press the object.

To animate an object

- 1. Select the object.
- 3. Press Object Animation.
- 4. Select options in the Type, Direction, Speed, Occurs and Repeats drop-down lists.

Locking objects

You can lock an object to prevent its modification, movement or rotation. Alternatively, you can lock an object but allow its movement or its movement and rotation.

You can remove this lock at any time.

Creating lesson activities

To lock an object

- 1. Select the object.
- 2. Press the object's menu arrow and then select Lock > Lock in Place.

You're unable to move, rotate or modify the object until you unlock it.



NOTE

If you press a locked object, a lock icon appears instead of a menu arrow.

To lock an object but allow its movement

- 1. Select the object.
- 2. Press the object's menu arrow and then select **Lock > Allow Move**.

You can move the object but you're unable to rotate or modify it until you unlock it.



NOTE

If you press a locked object, a lock icon appears instead of a menu arrow.

To lock an object but allow its movement and rotation

- 1. Select the object.
- 2. Press the object's menu arrow and then select Lock > Allow Move and Rotate.

You can move and rotate the object but you're unable to modify it until you unlock it.



NOTE

If you press a locked object, a lock icon appears instead of a menu arrow.

To unlock an object

- 1. Select the object.
- 2. Press the object's lock icon and then select **Unlock**.

Using advanced page features

You can use the following advanced page features when creating lesson activities:

- Student page borders
- Page recording
- · Page backgrounds and themes

Displaying student page borders

If your students use SMART Notebook SE (Student Edition) software to answer questions and take assessments, you might find it helpful when you create question pages to display a student page border showing the page area that will be visible on your students' computer screens.



NOTE

This procedure applies only if you're using SMART Response software in CE mode.

To display a student page border

1. Select View > Alignment.

The Alignment dialog box appears.

- 2. Press Student Page Border.
- 3. Select the Show a border around the area that will be visible in SMART Notebook SE during an assessment check box.
- 4. Select Preset value, and then select a screen resolution from the drop-down list.

Select Custom value, and then type the width and height of your students' screens in the boxes.

5. Press OK.

A colored border appears on the page around the area your students will be able to view on their computer screens.

Recording pages

The Page Recording options enable you to record your actions on the current page.



NOTE

SMART Recorder is a different but similar tool. Using SMART Recorder, you can record your actions in programs other than SMART Notebook software. With SMART Recorder, you can record a full screen, specified window or rectangular portion of the screen. If you connect a microphone to your computer, you can also record audio.

To record a page

- Press Page Recording.

Creating lesson activities

3. Press Start Recording.

The **Start Recording** button is replaced with the **Stop Recording** button, the **Play** button is disabled, and a red circle appears in the upper left corner of the page.

- 4. Perform the actions that you want to record on the current page.
- 5. When you finish performing these actions, press **Stop Recording**.

The **Stop Recording** button is replaced with the **Start Recording** button, the **Play** button is enabled, and a playback toolbar appears on the page.



To play a page recording

1. Display the page.

If the page includes a page recording, a playback toolbar appears on the page.

- 2. Press Play .
- To pause the playback

Press Pause II.

To stop the playback

Press **Stop**

To rewind the playback

Press **Rewind** .

To remove a page recording

1. Display the page.

If the page includes a page recording, a playback toolbar appears on the page.

2. To remove the recording, press Close S on the toolbar.

Applying page backgrounds and themes

You can define the appearance of pages' backgrounds using the Properties tab or the Gallery.

Applying backgrounds using the Properties tab

You can set a page's background to a solid colour, a gradient of two colours, a pattern or a picture using the Properties tab.

To apply a background

1. Select Format > Page > Set Background Fill.

The Properties tab displays Fill Effects options.

2. Select a fill style:

Fill style	Procedure	
None (transparent)	Select No fill.	
Solid colour	a. Select Solid fill .	
	b. Do one of the following:	
	 Select one of the 40 colours in the palette. 	
	 Press More and then select a colour in the dialogue box. 	
	 Press the eyedropper and then select a colour on the screen. 	
Gradient of two	a. Select Gradient fill.	
colours	b. For each colour, do one of the following:	
	 Select one of the 40 colours in the palette. 	
	 Press More and then select a colour in the dialogue box. 	
	 Press the eyedropper and then select a colour on the screen. 	
	c. Select an option in the <i>Style</i> drop-down list.	
Pattern	a. Select Pattern fill.	
	b. Select a pattern.	
	c. Press Foreground colour, select a colour in the dialogue box and then press OK.	
	d. Press Background colour , select a colour in the dialogue box and then press OK .	
Picture	a. Select Image fill.	
	b. Press Browse .	
	The <i>Insert Image File</i> dialogue box appears.	
	c. Browse to and select the picture that you want to use as a background and then press Open .	
	NOTE	
	If you insert a large picture, a dialogue box may appear and prompt you to either reduce the picture's file size or retain the picture's file size. For more information, see <i>Setting image optimisation preferences</i> on page 159.	

To remove a background

1. Select Format > Page > Set Background Fill.

The Properties tab displays Fill Effects options.

2. Select No fill.

Applying backgrounds and themes using the Gallery

You can set a page, all the pages in a group or all the pages in a file using a background or theme from the Gallery.

To apply a background or theme

- 1. If the Gallery isn't visible, press **Gallery** ■.
- 2. Select **My Content** in the Gallery's category list to view your own backgrounds and themes (see *Creating themes* on the next page).

OR

Select Gallery Essentials to view backgrounds and themes you installed with the software.

3. Select Backgrounds and Themes.

The Gallery displays thumbnails of the available backgrounds and themes.

- 4. Press the thumbnail of the theme that you want to apply.
- 5. Press the thumbnail's menu arrow and then select **Insert in Notebook**.

The Insert Theme dialogue box appears.

6. Select **Insert theme on all pages** to apply the background or theme to all pages in a file.

OR

Select **Insert theme on all pages of current group** to apply the background or theme to all pages in the current group.

OR

Select **Insert theme on current page only** to apply the background or theme to the current page.

7. Press OK.

To remove a background or theme

- 1. Right-click the page.
- 2. Select Remove Theme.

Select From All Pages to remove the background or theme from all the pages to which you applied it.

OR

Select From Page to remove the background or theme from the selected page only.

Creating themes

You can use themes to customise pages. You can create a theme and add it to the Gallery so that it's available in a convenient location. You can then apply this theme to a page, all pages in a group or all pages in a file.

The Gallery also includes some themes.

To create a theme

- 1. Select Format > Theme > Create New Theme.
- 2. Type a name for the theme in the *Theme name* box.
- 3. Set the background in the same way that you would for a page (see *Applying page backgrounds and themes* on page 106).
- 4. Add and modify objects on the theme in the same way that you would on a page (see *Creating basic objects* on page 31).
- 5. Press Save.

The theme appears in the My Content category of the Gallery.

To create a theme based on the current page

- 1. Select Format > Theme > Create New Theme From Page.
- 2. Type a name for the theme in the *Theme name* box.
- 3. Press Save.

The theme appears in the My Content category of the Gallery.

Creating example lesson activities

This section includes example lesson activities that you can create and also explains how to create other types of lesson activities.

Creating a matching lesson activity

NOTE

You'll complete the following tasks when creating matching lesson activities:

- · Using the Activity Builder
- Adding sounds to objects (see Adding sounds to objects on page 102)

The Activity Builder enables you to create matching activities, sorting activities, labelling activities, games and more using your own content.

Using the Activity Builder, you define one object on the page as an activity object. You then define which objects on the page will be accepted and which will be rejected when you drag the objects over the activity object.

To create a matching lesson activity

- 1. Create the object you want to use as the activity object and the objects that you want to accept or reject when dragged to the activity object.
- Press Add-ons and then press Activity Builder.
- 3. Select the object you want to use as the activity object and then press Edit.
- 4. Drag the objects you want to accept to the Accept these objects list.

A green tick appears beside objects that you select to accept.

5. Drag the objects that you want to reject to the Reject these objects list.

A red X 23 appears beside objects that you select to reject.



NOTES

- To quickly select any remaining objects on the page to accept or reject, press Add All Remaining in the appropriate list.
- To remove an object from a list, drag it to the rubbish bin icon ■.
- 6. Press Done.

To change a matching lesson activity's settings

- 1. Press Add-ons and then press Activity Builder.
- 2. Select the activity object and then press Edit.



If you don't know which object on the page is the activity object, click Identify. Blue diagonal lines appear for three seconds over any activity objects on the page.

Creating lesson activities

- 3. Press Settings.
- 4. Select the desired animation for accepted objects in the first **Animation** drop-down list.
- Optionally, select the Also play the object's sound tickbox to play sounds attached to
 accepted objects when they're dragged over the activity object (see Adding sounds to
 objects on page 102).
- 6. Select the desired animation for rejected objects in the first **Animation** drop-down list.
- Optionally, select the Also play the object's sound tickbox to play sounds attached to rejected objects when they're dragged over the activity object (see Adding sounds to objects on page 102).
- 8. Press Done.

To present a matching lesson activity

- 1. Drag the objects (or get students to drag the objects) to the activity object.
 - If the object is accepted, the accepted object animation plays (fade out by default).
 - o If the object is rejected, the rejected object animation plays (bounce back by default).
- 2. Press Add-ons de, press Activity Builder and then press Reset All when you've finished.

To remove a matching lesson activity

- 1. Press Add-ons dand then press Activity Builder.
- 2. Select the activity object and then press Clear Properties.

Creating a hide-and-show lesson activity

NOTE

You'll complete the following tasks when creating hide-and-show lesson activities:

- Moving objects (see Moving objects on page 58)
- Locking objects (see Locking objects on page 103)
- Resizing objects using the scaling gesture (see *Using the scale gesture* on page 65)

You can hide an object and then reveal it using several techniques:


- Add a Screen Shade to a page. During the presentation, gradually remove the shade to
 reveal the underlying text and graphics when you're ready to discuss them (see *Using the*Screen Shade on page 126).
- Cover the object with digital ink and then erase the digital ink (see *Writing, drawing and erasing digital ink* on page 32).

- Cover the object with another object and then change the order of the objects in the stack (see *Rearranging stacked objects* on page 61).
- Use the object animation feature (see *Animating objects* on page 103).


Alternatively, you can hide an object behind a locked object and then use the scaling gesture to enlarge and show the hidden object if you're using a SMART interactive product that supports multitouch gestures.

To create a hide-and-show lesson activity


1. Create or insert the object that you want to hide.



2. Create or insert the object that you want to lock.



3. Move the object that you want to lock so that it covers the object that you want to hide.



- 4. Select the object you want to lock, press its menu arrow, and then select Locking > Lock in Place.
- 5. Use the scaling gesture to enlarge and show the hidden object whilst keeping the locked object in place (see Using the scale gesture on page 65).



Creating a reveal lesson activity

NOTE


You'll complete the following tasks when creating reveal lesson activities:

- Creating tables (see Creating tables on page 44)
- Resizing cells (see Resizing tables, columns or rows on page 50)
- Filling a table's background with a picture (see Changing a table's properties on page 48)
- Adding objects to cells (see Adding objects to tables on page 46)
- Adding and removing cell shades (see *Using cell shades* on page 126)


Creating lesson activities

You can use tables and cell shades to create a variety of reveal lesson activities. The following are two examples:

 A puzzle-style reveal lesson activity where you reveal parts of a picture until students can guess what the picture is.



 A memory-style reveal lesson activity where you reveal the contents of the cell and then ask students to choose other cells until they find the cell with matching contents.



To create a puzzle-style reveal lesson activity

- 1. Create a table with the number of cells that you want to include in the reveal lesson activity (see *Creating tables* on page 44).
- 2. Resize the cells as appropriate (see Resizing tables, columns or rows on page 50).
- Select the table, press the table's menu arrow and then select **Properties**.
 The *Properties* tab appears.
- 4. Press Fill Effects.
- 5. Select **Image fill**, press **Browse**, browse to and select the picture you want to use in the reveal lesson activity and then press **Open**.
- 6. Select Scale image to fit.
- 7. Press the table's menu arrow and then select **Add Table Shade**.

To create a memory-style reveal lesson activity

- 1. Insert the objects that you want to include in the lesson activity.
- 2. Create a table with the number of cells that you want to include in the reveal lesson activity (see *Creating tables* on page 44).

Creating lesson activities

- 3. Resize the cells as appropriate (see Resizing tables, columns or rows on page 50).
- 4. Drag the objects into the cells of the table.
- 5. Press the table's menu arrow and then select Add Table Shade.

To present a reveal lesson activity

Press a individual cell's cell shade to reveal the contents of the cell.

To hide the cell behind the cell shade, press in the corner of the cell.

Creating other types of lesson activities

The Lesson Activity Toolkit and Lesson Activity Examples in the Gallery include interactive objects you can use to create lesson activities. For more information on the Lesson Activity Toolkit, the Lesson Activity Examples and the Gallery in general, see *Inserting content from the Gallery* on page 71.

The SMART Exchange website includes thousands of lesson plans, question sets and other content that you can download and then open in SMART Notebook software. For more information on the SMART Exchange website, see *Inserting content from the SMART Exchange website* on page 76.

Accessing XC Collaboration

SMART Notebook software includes the basic version of XC Collaboration. The basic version of XC Collaboration is a free add-on by Frieland that enables students to text ideas from their mobile devices to a SMART Notebook page for the entire class to see. You can also access the online tour to learn how to use XC Collaboration.

IMPORTANT

Go to xc-collaboration.com to purchase a licence for the full version of XC Collaboration.

To access XC Collaboration

- 1. Press Add-ons deand then press XC Collaboration.
- 2. Press Connect.

Creating lesson activities

To access the XC Collaboration online tour

- 1. Press Add-ons **d**, and then press **XC Collaboration**.
- 2. Press Start tour.

NOTE

You can also access help in the following ways:

- Press next to the feature that you need assistance with.
- Go to xc-collaboration.com/support.

Chapter 10

Presenting lesson activities and facilitating collaboration

Preparing before presenting	118
Setting the page display	118
Zooming in and out	119
Panning pages	120
Displaying pages in Full Screen view	120
Displaying pages in Transparent Background view	122
Displaying pages in Dual Page view	123
Displaying links	124
Moving windows between screens	125
Adjusting the volume	125
Using presentation tools whilst presenting	125
Using the Screen Shade	126
Using cell shades	126
Using the Magic Pen	127
Selecting the Magic Pen	127
Using the Magic Pen to create fading objects	128
Using the Magic Pen to open a magnification window	128
Using the Magic Pen to open a spotlight window	130
Using the Text Pen	130
Writing with the Text Pen	131
Editing with the Text Pen	132
Using the Standard pen type to create fading objects	133
Using measurement tools	133
Using the ruler	133
Using the protractor	135
Using the Geodreieck protractor	137
Using the compass	139
Clearing or resetting pages after presenting	140
Clearing pages	141
Resetting pages	142
Enabling two people to use an interactive whiteboard	143
Enabling two people to use a SMART Board D600 series interactive whiteboard	144
Enabling two people to use a SMART Board 800 series interactive whiteboard	144
Selecting tools	145

After creating lesson activities in SMART Notebook software, you can present the lesson activities to students using your interactive product and the presentation features of the software.

In addition to presenting lesson activities to students, you can facilitate collaboration in your classroom using SMART Notebook software and your interactive product. Specifically, you can enable two people to use your SMART Board D600 series or 800 series interactive whiteboard at the same time.

Preparing before presenting

When you have completed your .notebook files and are ready to present them to students, save the files on a CD, DVD or USB drive. This enables you to access and display the files by inserting the CD, DVD or USB drive into the computer connected to the interactive product. Alternatively, make the files accessible on your local area network, and then browse to them on the interactive product.

Next, prepare for presenting by doing the following:

- · Set the page display
- · Display any links in the file
- If you have multiple interactive products in your classroom, move windows to the appropriate screens
- If you're presenting video or sound files, adjust the volume

Setting the page display

You can zoom in and out using the View Screens button or multitouch gestures (if your interactive product supports multitouch gestures).

In addition, SMART Notebook software includes the following views:

- Full Screen view expands the page area to fill the interactive screen by hiding the title bar, toolbar, taskbar and sidebar.
- Transparent Background view enables you to see the desktop and windows behind the SMART Notebook software window and continue to interact with the open, transparent page.
- Dual Page view displays two pages side-by-side.

Presenting lesson activities and facilitating collaboration

Zooming in and out

You can zoom in and out using the View Screens button or multitouch gestures (if your interactive product supports multitouch gestures).

To zoom in or out using the View Screens button

- 1. Press View Screens .
- 2. Select a magnification level between 50% and 300%.

OR


Select Entire Page to make the entire page fit your display.

OR

Select Page Width to set the page's width to the same width as your display.


To zoom in or out using multitouch gestures

Drag your fingers in opposite directions to zoom in.



OR

Drag your fingers towards each other to zoom out.



A message appears, displaying the current zoom level.




Presenting lesson activities and facilitating collaboration

Panning pages

If your interactive product supports the pan gesture, you can pan a page when zoomed in (see Zooming in and out on the previous page).

To pan

- 1. Using two fingers on the same hand, press and hold the screen.
- 2. Keeping your fingers on the screen, move up, down, left or right.



3. When you reach the area that you want to view, release your fingers.

Displaying pages in Full Screen view

In Full Screen view, SMART Notebook software expands the page to fill the screen by hiding the other user interface elements. You can still access commonly used commands using the Full Screen toolbar.



Before displaying a page in Full Screen view, select View > Full Screen Page Border, and then select the appropriate aspect ratio for your interactive product. A blue line appears, indicating the portion of the page that will appear in Full Screen view without scrolling.

This feature is useful when you're creating content that you want to present in Full Screen view.

Presenting lesson activities and facilitating collaboration

To display a page in Full Screen view

Press View Screens , and then select Full Screen.

The page expands to fill the screen, hiding the other user interface elements, and the *Full Screen* toolbar appears.



Button	Command	Action	
4	Previous Page	Display the previous page in the file.	
-	Next Page	Display the next page in the file.	
	More Options	Open a menu of options.	
↔	Page Width	Change the zoom level to the page's width.	
		TIP	
		This is useful if you're using a widescreen interactive product and gray bars appear on the sides of the page.	
‡	Entire Page	Change the zoom level to Full Page view.	
<u> </u>	Exit Full Screen	Return to the standard view.	
+	Toolbar Options	Display additional toolbar buttons.	

NOTES

- The toolbar displays the current page number and the total number of pages in the file.
- If SMART Response software is installed, additional buttons appear that enable you to insert questions and administer assessments.

To display more toolbar buttons

Press Toolbar Options .

The toolbar expands to include the following buttons:

Button	Command	Action	
5 1	Blank Page	Insert a new, blank page in the current file.	
5	Undo	Reverse the effect of the last action.	

Button	Command	Action	
K	Select	Select objects on the current page.	
P.	Magic Pen	Create objects that slowly fade, open a magnification window or open a spotlight window (see <i>Using the Magic Pen</i> on page 127).	

Displaying pages in Transparent Background view

Using Transparent Background view, you can see the desktop and windows behind the SMART Notebook software window and continue to interact with the open, transparent page. You can draw in digital ink on a transparent page and save your notes in the file. You can also display measurement tools, take screen captures and more. If an area of the screen doesn't include any SMART Notebook software objects, you can select and interact with the desktop and applications behind the SMART Notebook software window.

To display a page in Transparent Background view

Press View Screens , and then select Transparent Background.

The background of the SMART Notebook software window becomes transparent, enabling you to see the desktop and program behind SMART Notebook software, but any objects on the .notebook file page remain visible.

The Transparent Background toolbar appears.



Button	Command	Action
ĸ	Select	Select objects on the current page or interact with desktop and application objects that aren't covered by a SMART Notebook software object.
P	Pens and Highlighters	Write or draw digital ink on the current page.
4	Previous Page	Display the previous page in the current file.
→	Next Page	Display the next page in the current file.
	More Options	Open a menu of options that enable you to add a screen shade, select different digital ink, select a Creative pen style, add straight lines, add shapes and more.
<u> </u>	Exit Transparent Background	Return to the standard view.
+	Toolbar Options	Display additional toolbar buttons.

Presenting lesson activities and facilitating collaboration

NOTES

- o The toolbar displays the current page number and the total number of pages in the file.
- o If SMART Response software is installed, additional buttons appear that enable you to insert questions and administer assessments.

To display more toolbar buttons

Press Toolbar Options .

The toolbar expands to include the following buttons:

Button	Command	Action	
<u>5</u> 1	Blank Page	Insert a new, blank page in the current file.	
9	Undo	Reverse the effect of the last action.	
×	Delete	Delete all selected objects.	
\bigcirc	Clear Page	Erase all digital ink and delete all objects from the page.	
•	Screen Capture Toolbar	Open the Screen Capture toolbar.	
	Insert Ruler	Insert a ruler on the page (see <i>Using the ruler</i> on page 133).	
P	Insert Protractor	Insert a protractor on the page (see <i>Using the protractor</i> on page 135).	
	Insert Geodreieck Protractor	Insert a Geodreieck protractor on the page (see <i>Using the Geodreieck protractor</i> on page 137).	
Â	Insert Compass	Insert a compass on the page (see <i>Using the compass</i> on page 139).	

Displaying pages in Dual Page view

You can display two pages side-by-side. You can draw, make notes, import files and add links on either page in the same way as you would on a single page.

When you're displaying dual pages, you can pin a page to continue displaying it in the page area while you view other pages in the Page Sorter.

To display a page in Dual Page view

Press View Screens , and then select Dual Page Display.

A second page appears. A red border indicates the active page.

Presenting lesson activities and facilitating collaboration

To pin a page

- 1. If you haven't done so already, display dual pages.
- 2. Select the page you want to continue displaying.
- 3. Select View > Dual Page Display > Pin Page.

Pin icons papear in the top corners of the pinned page.

To unpin a page

Clear the selection of View > Dual Page Display > Pin Page.

To return to standard view

Press View Screens , and then select Single Page Display.

Displaying links

You can attach a copy of a file, a shortcut to a file, a link to a webpage or a sound file to any object on a page (see Adding links to objects on page 100). You can display an animated indicator around each object that has a link.

To display links when a page opens

Select View > Show All Links When Page Opens.

Each time that you open a page, an animated indicator appears around each object that has a link. Depending on how you define the links, each indicator surrounds either the entire object or an icon in the object's lower-left-hand corner. The indicators disappear automatically after several seconds.



NOTE

Clear the selection of View > Show All Links When Page Opens to stop displaying links when you open a page.

To display links on the current page

Select View > Show All Links.

An animated indicator appears around each object that has a link. Depending on how you define the links, each indicator surrounds either the entire object or an icon in the object's lower-left-hand corner. The indicators disappear automatically after several seconds.

Presenting lesson activities and facilitating collaboration

Moving windows between screens

You can operate multiple interactive products from the same computer. You can split the computer display over two or more screens, or you can display some programs on one screen and other programs on another. For more information, see Connecting multiple interactive whiteboards to one computer (smarttech.com/kb/000315).

If you connect multiple interactive products to one computer, you can move windows from one screen to another.

To move a window from one screen to another

1. If you haven't already done so, display the window.



NOTE

You can move a window only if it's neither maximised nor minimised.

- 2. Press and hold the window on the first screen with your finger.
- 3. Press the second screen with a finger on your other hand.
- 4. Lift your finger from the first screen.

The window disappears from the first screen and appears on the second screen.

Adjusting the volume

If you're presenting a video or sound file and want to adjust volume, you can do so pressing the **Volume Control** button and then adjusting your operating system's volume controls.



NOTE

Ensure your speakers are turned on.

To add this button to the toolbar, see Customising the toolbar on page 155.

Using presentation tools whilst presenting

Whilst presenting lesson activities to students, you can use the following tools:

- Screen Shade
- Cell shades
- Magic Pen
- Text Pen (to write editable ink)
- Standard pen type (to create fading objects)

Presenting lesson activities and facilitating collaboration

- Measurement tools
 - o Ruler
 - Protractor
 - Geodreieck protractor
 - o Compass

Using the Screen Shade

If you want to cover information and reveal it slowly during a presentation, you can add a Screen Shade to a page.

If you add a Screen Shade to a page and save the file, the Screen Shade appears over the page the next time you open the file.

To add a Screen Shade to a page

Press Show/Hide Screen Shade .

A Screen Shade appears over the entire page.

To reveal part of the page

Drag one of the Screen Shade's resize handles (the small circles at the edges of the Screen Shade).

To remove the Screen Shade from a page

Press Show/Hide Screen Shade -.

ΟR

Press Close in the upper right-hand corner of the Screen Shade.

Using cell shades

You can add a cell shade to a table cell. This enables you to reveal the information in the cells during a presentation.

NOTES

- You must remove the cell shade if you want to change the cell's properties; insert columns or rows; remove columns, rows or cells; or split or merge cells.
- You can also add a screen shade to cover an entire page (see Using the Screen Shade above).

Presenting lesson activities and facilitating collaboration

To add a cell shade

- 1. Select the cell.
- 2. Press the cell's menu arrow and then select Add Cell Shade.

To show and hide the contents of a cell

1. Press the cell shade.

The cell shade disappears, showing the contents of the cell.

2. Press in the top left-hand corner of the cell.

The cell shade appears, hiding the contents of the cell.

To remove a cell shade

- 1. Select the cell.
- 2. Press the cell's menu arrow and then select Remove Cell Shade.

Using the Magic Pen

The Magic Pen enables you to do the following:

- Create an object that slowly fades
- · Open a magnification window
- · Open a spotlight window


Selecting the Magic Pen

Before you can use the Magic Pen, you must select it.

To select the Magic Pen

1. Press Pens W.

The Pens tool buttons appear.



2. Press Pen Types and then select Magic Pen.

Presenting lesson activities and facilitating collaboration

Using the Magic Pen to create fading objects

You can create an object that slowly fades using the Magic Pen.



NOTE

Fading objects are not saved in .notebook files.

To create a fading object

- 1. Select the Magic Pen (see Selecting the Magic Pen on the previous page).
- 2. Using your finger or a pen, write or draw objects on the interactive screen.

The objects slowly fade.

To set the number of seconds before the object fades

- 1. Select the Magic Pen (see Selecting the Magic Pen on the previous page).
- 3. Press Fill Effects.
- 4. Enter or select the number of seconds before the object fades in the Fade time drop-down list.




You can save your changes to the Magic Pen tool's default settings by clicking Save Tool Properties (see Saving tool settings on page 58).

Using the Magic Pen to open a magnification window

You can open a magnification window using the Magic Pen.

To open a magnification window

- 1. Select the Magic Pen (see Selecting the Magic Pen on page 127).
- Using your finger or a pen, draw a square or rectangle on the interactive screen.
 A magnification window appears.



TIP

You can draw a square but have it fade rather than open a magnification window by using the Standard pen type (see *Using the Standard pen type to create fading objects* on page 133).

3. Do the following:

- To reduce the magnification window's size, press in the middle of the window and then drag to the left.
- To increase the magnification window's size, press in the middle of the window and then drag to the right.
- o To move the magnification window, press near the edge of the window and then drag it.
- 4. Press Close when you've finished.

Presenting lesson activities and facilitating collaboration

Using the Magic Pen to open a spotlight window

You can open a spotlight window using the Magic Pen.

To open a spotlight window

- 1. Select the Magic Pen (see Selecting the Magic Pen on page 127).
- Using your finger or a pen, draw a circle or ellipse on the interactive screen.
 A spotlight window appears.



TIP

You can draw a circle but have it fade rather than open a magnification window by using the Standard pen tool (see *Using the Standard pen type to create fading objects* on page 133).

3. Do the following:

- To reduce the spotlight window's size, press in the middle of the window and then drag to the left.
- To increase the spotlight window's size, press in the middle of the window and then drag to the right.
- o To move the spotlight window, press near the edge of the window and then drag it.
- 4. Press Close When you've finished.

Using the Text Pen

The Text Pen enables you to do the following:

Presenting lesson activities and facilitating collaboration

- Write notes that automatically convert into editable text
- · Edit the text as you work without touching a keyboard


Writing with the Text Pen

You can write notes that automatically convert to editable text using the Text Pen.

To write editable text

1. Press Pens W.

The Pens tool buttons appear.



- 2. Press Pen Types and then select Text Pen.
- 3. Select a line type.



Write neat, printed characters on a horizontal line. Although SMART Notebook software can convert slanted or cursive writing, it doesn't always do so consistently.

4. Write digital ink notes on the page.

Your handwriting converts to typed text. Accept and reject icons appear beside the typed text.



Press

olimits to accept the typed text.

OR

Press to restore your handwritten notes.



- You can perform this action whilst the Text Pen is active without having to switch to the Select tool
- The typed text is accepted by default if you don't press one of the icons.

Presenting lesson activities and facilitating collaboration

Editing with the Text Pen

You can apply mark-ups and make revisions to editable text using the Text Pen. You can delete unwanted text by drawing a strike-through line through the text. You can also apply other mark-ups to insert spaces, to insert text and to replace text with new text.



Write your mark-ups in a different colour from your editable text. This makes it easier for students to see your edits when you're presenting writing lessons.

Examples of available mark-ups are defined in the following table:

Edit	Instruction	Example	
Delete text	Draw a strike-through line through the text.	SMART SMART Notebook	
Insert space	Draw a vertical line in the text.	SMARTNotebook	
Insert text	 Draw a caret ^ symbol where you want to insert text. Write the new text in the text box that appears. Words that most resemble what you've written display underneath your handwriting. Select a word to insert it as typed text. You can also press to automatically select the word that appears as bold text. OR Press to cancel insert text. 	SMART software Notebook Notebook	
Replace text	 Draw a circle around the text that you want to replace. Write the replacement text in the box that appears. Words that most resemble what you've written display underneath your handwriting. Select a word to replace the typed text. You can also press to automatically select the word that appears as bold text. OR Press to cancel replace text. 	SMART Response software Notebook Notebook Note	

Presenting lesson activities and facilitating collaboration

Using the Standard pen type to create fading objects

You can create freehand objects that fade after a specified period of time using the Pens tool.




NOTE

You can also create freehand objects that fade after a specified period of time using the Magic Pen tool (see Using the Magic Pen to create fading objects on page 128).

To write or draw fading digital ink

1. Press Pens W.

The Pens tool buttons appear.



- 2. Press Pen Types and then select Pen.
- 3. Select a line type.
- 5. Press Fill Effects.
- 6. Select the Enable ink to fade after you write it tickbox and then enter or select the number of seconds between the time you write or draw the digital ink and the time it fades in the Fade time drop-down list.
- 7. Write or draw digital ink on the page.

Using measurement tools

Using the SMART Notebook software measurement tools, you can insert a ruler, protractor, Geodreieck protractor or compass into a page.

Using the ruler


You can insert a ruler into a page and then manipulate its size, length, rotation and location and draw along its edges.

To insert a ruler

Press **Measurement Tools** And then select **Insert Ruler** .

A ruler appears.

Presenting lesson activities and facilitating collaboration



To move the ruler

Press the middle of the ruler (displayed as a darker shade of blue) and then drag the ruler to a different position on the page.

To resize the ruler

- 1. Select the ruler.
- 2. Drag the ruler's resize handle (the circle in the lower-right-hand corner) to increase or reduce the ruler's size.

To lengthen the ruler (without changing its scale)

Press the ruler's far edge, between the menu arrow and the resize handle and then drag away from the ruler.

To shorten the ruler (without changing its scale)

Press the ruler's far edge, between the menu arrow and the resize handle and then drag towards the middle of the ruler.

To rotate the ruler

Press the top or bottom edge of the ruler (displayed as a lighter shade of blue) and then drag the ruler in the direction that you want to rotate it.

The ruler displays the current rotation in degrees.

To reverse the measurements

Press the ruler's flip symbol \$\mathbb{I}\$.


If the metric measurements appeared on the top edge of the ruler, they now appear on the bottom edge and vice versa.

Presenting lesson activities and facilitating collaboration

To draw using a pen and the ruler

1. Press Pens W.

The Pens tool buttons appear.



- 2. Press Pen Types and then select Pen or Calligraphic Pen.
- 3. Select a line type.
- 4. Draw along the edge of the ruler.

Digital ink appears in a straight line along the edge of the ruler.

To remove the ruler

- 1. Select the ruler.
- 2. Press the ruler's menu arrow and then select **Delete**.


Using the protractor

You can insert a protractor into a page, manipulate its size, rotation and location and then draw along its edges.

To insert a protractor

Press Measurement Tools R and then select Insert Protractor .

A protractor appears.



Presenting lesson activities and facilitating collaboration

To move the protractor

Press the inner part of the protractor (displayed as a darker shade of blue) and then drag the protractor to a different position on the page.

To resize the protractor

Press the inner circle of numbers and then drag away from the protractor to enlarge it or toward the centre of the protractor to shrink it.


To rotate the protractor

Press the outer circle of numbers and then drag the protractor in the direction you want to rotate it.

The protractor displays the current rotation in degrees.

To display the protractor as a complete circle

1. Press the blue circle next to the 180 label on the inner circle of numbers.




2. Press the blue circle again to return to the semi-circle.

Presenting lesson activities and facilitating collaboration

To draw using a pen and the protractor

1. Press Pens W.

The Pens tool buttons appear.



- 2. Press Pen Types and then select Pen or Calligraphic Pen.
- 3. Select a line type.
- 4. Draw along the edge of the protractor.

Digital ink appears in an arc along the edge of the protractor.

To display angles using the protractor

- 1. Select the protractor.
- 2. Drag the green circle until it shows the correct angle for the first of two intersecting lines.
- 3. Drag the white circle until it shows the correct angle for the second of two intersecting lines.
- 4. Press the green arrow in the bottom corner.

The lines and the angle between them appear as a separate object.

To remove the protractor

- 1. Select the protractor.
- 2. Press the protractor's menu arrow and then select **Delete**.


Using the Geodreieck protractor

You can insert a Geodreieck protractor (also known as a set square or T-square) on a page and then manipulate its size, rotation and location.

To insert a Geodreieck protractor

Press Measurement Tools And then select Insert Geodreieck .

A Geodreieck protractor appears.



To move the protractor

Press the inner part of the protractor (within the semi-circle) and then drag the protractor to a different position on the page.

To resize the protractor

Press the semi-circle and then drag away from the centre of the protractor to make it bigger or towards the centre of the protractor to make it smaller.

To rotate the protractor


Press the outer part of the protractor (outside of the semi-circle) and then drag the protractor in the direction you want to rotate it.

The protractor displays the current rotation in degrees.

To draw using a pen and the Geodreieck protractor

1. Press Pens W.

The Pens tool buttons appear.



- 2. Press Pen Types and then select Pen or Calligraphic Pen.
- 3. Select a line type.
- 4. Draw along the edge of the protractor.

Digital ink appears in a straight line along the edge of the protractor.

Presenting lesson activities and facilitating collaboration

To remove the protractor

- 1. Select the protractor.
- 2. Press the protractor's menu arrow and then select **Delete**.


Using the compass

You can insert a compass into a page, manipulate its width, rotation and location and then use it to draw circles and arcs.

To insert a compass

Press Measurement Tools \P and then select Insert Compass $ilde{\mathbb{A}}$.

A compass appears.



To move the compass

Press the arm of the compass that holds the spike and then drag the compass to a different position on the page.

To widen the compass

1. Press the arm of the compass that holds the pen.

Two blue arrows appear.

2. Drag to change the angle between the spike and the pen.

The number on the compass's handle displays the current angle between the spike and the pen.

To flip the compass

Press the compass's flip symbol .

The compass's pen appears on the opposite side of the spike.

To rotate the compass (without drawing)

Press the compass's rotation handle (the green circle) and then drag the compass in the direction that you want to rotate it.

Presenting lesson activities and facilitating collaboration

To draw using the compass

1. Press the compass's pen tip.


The cursor changes to a pen symbol.

2. Drag the compass in the direction that you want to rotate it.

To change the colour of the compass's pen

1. Press Pens W.

The Pens tool buttons appear.



- 2. Press Pen Types and then select Pen.
- 3. Select a line type.

The colour of the compass's pen changes to display its new colour.

To remove the compass

- 1. Select the compass.
- 2. Press the compass's menu arrow and then select **Delete**.

Clearing or resetting pages after presenting

After presenting a lesson activity to students, you can clear or reset the pages in your .notebook files to use the files again for future lesson activities.

Presenting lesson activities and facilitating collaboration

Clearing pages

You can erase digital ink and delete individual objects from a page. You can also clear all objects or all digital ink objects from a page simultaneously.



NOTE

You're unable to clear objects locked in place (see Locking objects on page 103) or infinitely cloned objects (see Cloning objects on page 64). To clear all objects from a page, you must unlock all locked objects and clear the selection of Infinite Cloner on any infinitely cloned objects.

To clear all objects from the page

- 1. If you haven't done so already, display the page that you want to clear.
- 2. Select Edit > Clear Page.



NOTES

- o This option is disabled if there are no objects on the page or if the objects are locked or infinitely cloned.
- You can also select this option by doing one of the following:
 - Right-clicking the page
 - Pressing the page's menu arrow in the Page Sorter
 - o Pressing the page's menu arrow whilst editing page groups (see Grouping pages on page 27)
 - Pressing Clear Page if it's included on the toolbar (see Customising the toolbar on page 155)
- You can clear all objects from multiple pages at the same time. Select the pages' thumbnails in the Page Sorter, press the menu arrow and then select Clear Page.

Presenting lesson activities and facilitating collaboration

To clear all digital ink objects from the page

- 1. If you haven't done so already, display the page that you want to clear.
- 2. Select Edit > Clear Ink from Page.

NOTES

- o This option is disabled if there is no digital ink on the page or if the digital ink is locked or infinitely cloned.
- You can also select this option by doing one of the following:
 - Right-clicking the page
 - Pressing the page's menu arrow in the Page Sorter
 - Pressing the page's menu arrow whilst editing page groups (see Grouping pages on page 27)
 - Pressing Clear Ink it's included on the toolbar (see Customising the toolbar on page 155)
- You can clear all digital ink objects from multiple pages at the same time. Select the pages' thumbnails in the Page Sorter, press the menu arrow and then select Clear Ink from Page.

Resetting pages

If you make changes to a page (without saving those changes), you can reset the page to the state that it was in before you made the changes.



NOTE

Resetting a page doesn't reset any Adobe Flash Player compatible files running on the page.

Presenting lesson activities and facilitating collaboration

To reset a page

- 1. If you haven't done so already, display the page you want to reset.
- 2. Select Edit > Reset Page.

A dialogue box appears, prompting you to confirm the reset.

NOTES

- This option is disabled if you haven't made changes to the page since last saving the
- You can also select this option by doing one of the following:
 - Right-clicking the page
 - Pressing the page's menu arrow in the Page Sorter
 - Pressing the page's menu arrow whilst editing page groups (see Grouping pages on page 27)
 - Pressing Reset Page if it's included on the toolbar (see Customising the toolbar on page 155)
- You can reset multiple pages at the same time. Select the pages' thumbnails in the Page Sorter, press the menu arrow and then select **Reset Page**.
- 3. Press Reset Page.

Enabling two people to use an interactive whiteboard

If you have a SMART Board D600 or 800 series interactive whiteboard, two people can create and manipulate objects in SMART Notebook software at the same time. How the two people do this depends on whether you have a SMART Board D600 series interactive whiteboard or a SMART Board 800 series interactive whiteboard.

Allowing two people to use an interactive whiteboard is useful in scenarios such as the following:

- Two students work on an assignment on the interactive whiteboard at the same time.
- A teacher and student work on an assignment on the interactive whiteboard at the same
- A teacher or student poses questions or problems on the interactive whiteboard and another student responds to these questions or problems

Enabling two people to use a SMART Board D600 series interactive whiteboard

If you're using a SMART Board D600 series interactive whiteboard, two users can use the interactive whiteboard simultaneously when SMART Notebook software is in Dual-User mode. In Dual-User mode, the screen is divided in half. Each user can press his or her half of the screen with a finger to left-click or drag objects, write using a pen tray pen and erase digital ink using the eraser. Each user can also access frequently used tools using his or her own Floating Tools toolbar.

You can press a toolbar button to switch between Single-User mode and Dual-User mode.

To display a file in Dual-User mode

Press View Screens and then select Dual Write Mode.

To return to Single-User mode

Press Exit \$\Psi\$.

Enabling two people to use a SMART Board 800 series interactive whiteboard

If you're using a SMART Board 800 series interactive whiteboard, two people can create and manipulate objects in SMART Notebook software at the same time. Both people can create and manipulate objects in any area of the SMART Notebook software page. Neither user is restricted to a particular section of the page.

Dual-user collaboration mode is enabled when you pick up a pen from the pen tray. One user creates or manipulates objects with his or her finger ("the touch user"). The other user creates or manipulates objects with the pen ("the pen user").



NOTE

In addition to enabling one touch user and one pen user to use the interactive whiteboard at the same time, you can enable two pen users or two touch users to use the interactive whiteboard at the same time. However, the two users must use the same tool.

Presenting lesson activities and facilitating collaboration

Selecting tools

To change tools or to set properties for touch, the touch user must press the appropriate button on the toolbar or control in the Properties tab with his or finger. The following is an example:



To change tools or to set properties for the pen, the pen user must press the appropriate button on the toolbar or control in the Properties tab with the pen. The following is an example:



NOTES

- If the pen user presses a button on the toolbar or sets a property with his or finger instead
 of the pen, SMART Notebook software changes the selected tool or property for the touch
 user rather than the pen user.
- When both the touch user and the pen user select multiple objects on the screen, the
 dashed border of the objects selected by the touch user will be a different colour than the
 dashed border of the object selected by the pen user.

Chapter 11

Enhancing SMART Notebook software with add-ons

Installing add-ons	147
Using add-ons	148
Identifying missing add-ons	148
Disabling and removing add-ons	148

Add-ons are extensions to SMART Notebook software created by SMART Technologies and by third-party software developers.

SMART Notebook software includes the Activity Builder add-on (see *Creating a matching lesson activity* on page 110) and the Alignment Tools add-on (see *Aligning objects* on page 60). You can install other add-ons from the SMART Exchange website to add specialised features to the software. In addition, you can manage all installed add-ons using the Add-on Manager.

Installing add-ons

You can search for, browse and install add-ons from the SMART Exchange website.

To install an add-on

1. Select Add-ons > Manage Add-ons.

The Add-on Manager appears.

2. Press Find More.

The SMART Exchange website opens in your web browser.

3. If you're new to the SMART Exchange website, press **Join for free** and then follow the on-screen instructions to create an account.

OR

If you have an account, press **Sign In** and then follow the on-screen instructions to log on to the SMART Exchange website with your account.

4. Search or browse for an add-on, and then download it to a temporary location on your computer.

Enhancing SMART Notebook software with add-ons

- 5. Double-click the add-on file.
- 6. Follow the on-screen instructions to install the add-on.

Using add-ons

After installing an add-on, you can use the features of that add-on like any other features in SMART Notebook software.

To view an add-on

- 1. Press Add-ons de.
- 2. Press the add-on's icon.

To view an add-on's version and other information

1. Select Add-ons > Manage Add-ons.

The Add-on Manager appears.

- 2. Press the add-on's name.
- 3. Press About.

Identifying missing add-ons

If you open a page in a .notebook file that requires an add-on that isn't installed or is disabled on your computer, a message appears at the top of the page. Press the message to open the Add-on Manager. The Add-on Manager identifies which add-on is required. You can then install that add-on (see *Installing add-ons* on the previous page) or enable it (see *Disabling and removing add-ons* below).

Disabling and removing add-ons

In some situations, you might want to disable or remove a previously installed add-on.

If you choose to disable an add-on, the add-on no longer appears in SMART Notebook software but is still installed on your computer. You can subsequently enable the add-on.

If you choose to remove an add-on, the add-on no longer appears in SMART Notebook software and is removed from your computer.

To disable an add-on

Select Add-ons > Manage Add-ons.

The Add-on Manager appears.

Enhancing SMART Notebook software with add-ons

- 2. Press the add-on's name.
- 3. Press Disable.



To enable the add-on again, press **Enable**.

To remove an add-on

1. Select Add-ons > Manage Add-ons.

The Add-on Manager appears.

- 2. Press the add-on's name.
- 3. Press Remove.



NOTE

You're unable to remove the Activity Builder add-on and the Alignment Tools add-on.

Chapter 12

Accessing RSS feeds with Notebook Connect

Finding, adding and deleting an RSS feed	151
Viewing RSS feed content	152
Bookmarking articles	153
Inserting images and video in the drawing area	.153

Using the Notebook Connect add-on, you can access the latest articles and receive continuously updated headlines from your favourite publications. You can add, delete and manage feeds, view and bookmark articles and insert images and videos from the articles into SMART Notebook software to share with your class. You can also access the SMART Central RSS feed, which is included by default.

To access Notebook Connect

Press Add-ons deand then press Notebook Connect.

Finding, adding and deleting an RSS feed

Many publications and media outlets offer RSS feeds for their content. You can search external websites for the RSS feed URL and then add that URL to Notebook Connect. You can also delete RSS feeds.

To add an RSS feed

- 1. Locate the URL of the RSS feed that you want to add.
- Press Add-ons d and then press Notebook Connect.
- Press Settings and then press Add Feed .
 A Feed URL box appears.
- 4. Type the full URL of the RSS feed in the box.

To delete an RSS feed

Press **Settings** and then press **Delete Feed** beside the feed's URL.

Viewing RSS feed content

After you add an RSS feed, you can access the feed's content and headlines from the main feed. You can mark articles as either read or unread, and you can refresh the main feed to ensure that you have access to the latest content.

To view content from the main feed

1. Press Main Feed and then select a feed from the drop-down menu.

A list of article thumbnails appears.

- 2. Select the headline on a thumbnail to view more details about the article.
- 3. Select View Article to open the full article.

OR

Select **Back** to return to the list of article thumbnails.



You can change the default software articles open in (see *To select the default software for opening articles* on the next page).

To mark an article as read

Press Main Feed and then press on the article thumbnail.

The icon changes to and the article appears grey.

To mark all articles as read

Press Main Feed and then press Mark all as read.

The icons change to so on all articles and the articles appear grey.

To mark an article as unread

Press **Main Feed** and then press on the article thumbnail.

The icon changes to and the article's appearance is restored.

To refresh the main feed

Press Main Feed and then select C.

To select the default software for opening articles

- Press Settings ⁽²⁾
- 2. Select Notebook if you want articles to open in SMART Notebook software.

OR

Select Your default Web browser if you want articles to open in your web browser.

Bookmarking articles

You can bookmark articles to view later by adding them to your favourites list. You can also delete articles from your favourites list.

To access your favourites list

1. Press Favourites *

A list of bookmarked articles appears.

To add an article to your favourites list

Press **Main Feed** and then press in the bottom right-hand corner of the article thumbnail.

To delete an article from your favourites list

Press **Favourites** \Rightarrow and then press \times in the bottom right-hand corner of the article thumbnail.

Inserting images and video in the drawing area

If an article contains an image or a video, you can insert it in the drawing area of SMART Notebook software.

To insert an image or a video in the drawing area

- 1. Press Add-ons deand then press Notebook Connect.
- Press Main Feed and then select a feed from the drop-down menu.

A list of article thumbnails appears.

3. Press son an article thumbnail to insert the article's image in the drawing area.

OR

Press , on an article thumbnail to insert the article's video in the drawing area.

Chapter 13

Maintaining SMART Notebook software

Customising the toolbar	155
Configuring SMART Notebook software	157
Changing the default program for .notebook files	157
Setting gesture preferences	158
Setting hardware acceleration preferences	159
Setting image optimisation preferences	159
Manually reducing the size of large pictures	159
Exporting optimised files	160
Setting default background colour preferences	160
Setting measurement tool preferences	161
Setting table cell padding preferences	162
Setting the language	163
Removing SMART software	164
Updating and activating SMART software	165
Updating SMART software	165
Activating SMART software	167
Purchasing a product key	168
Activating SMART software with a product key	168
Sending feedback to SMART	169

This chapter explains how to maintain SMART Notebook software.

Customising the toolbar

The SMART Notebook software toolbar enables you to select and use a variety of commands and tools. You can customise the toolbar so that it includes the tools that you use most frequently.

After adding or removing toolbar buttons, you can restore the default set of toolbar buttons. You can also restore the tools' default settings if you customised and saved the settings using the Properties tab (see *Saving tool settings* on page 58).

To add or remove toolbar buttons

1. Click Customise the toolbar .

OR

Right-click the toolbar.

The Customise Toolbar dialogue box appears.

- 2. Press Actions or Tools.
- 3. Do the following:
 - o To add a button to the toolbar, press its icon in the dialogue box and then drag it to the
 - o To remove a button from the toolbar, press its icon in the toolbar and then drag it away from the toolbar.
 - o To rearrange the buttons, press an icon in the toolbar and then drag it to a new position in the toolbar.

NOTES

- You can only add, remove and rearrange buttons in the panel of the toolbar that you selected in step 2. For example, if you pressed Actions in step 2, you can only add, remove and rearrange buttons in the Actions panel.
- To span a button across rows, drag and hold it between two columns of buttons.



If you're using a smaller screen resolution, only span one or two buttons across rows to prevent issues when the toolbar is wider than the SMART Notebook software window.

4. Press Done.

To restore the default set of toolbar buttons

1. Click Customise the toolbar .



OR

Right-click the toolbar.

The Customise Toolbar dialogue box appears.

2. Press Restore Default Toolbar.

To restore the tools' default settings

1. Click Customise the toolbar .

OR

Right-click the toolbar.

The Customise Toolbar dialogue box appears.

2. Press Restore Default Tool Properties.

Configuring SMART Notebook software

This section explains how to configure SMART Notebook software.

Changing the default program for .notebook files

If you install a SMART program other than SMART Notebook software that can open .notebook files, you can set that program to be the default for .notebook files. If you want, you can change the default program back to SMART Notebook software later.

To change the default program when you open a file

- 1. Open a .notebook file using SMART Notebook software (see *Opening files* on page 13).
 - A message appears asking whether you want to change the default program for .notebook files to SMART Notebook software.
- 2. Press Yes.

To change the default program using the Preferences dialogue box


1. Select Edit > Preferences.

The SMART Notebook Preferences dialogue box appears.

- 2. Press General.
- 3. Press Make Default.
- 4. If you want a message to appear when you open a .notebook file and your default program isn't SMART Notebook software, select Tell me if SMART Notebook software isn't the default program for .notebook files.
- 5. Press OK.

Setting gesture preferences

You can interact with objects in SMART Notebook software using gestures, including the shake gesture and the press-and-hold gesture.



The shake and press-and-hold gestures are enabled by default. However, you can choose to disable them if you find that you or your students frequently invoke the gestures by accident.

To disable the shake gesture

1. Select Edit > Preferences.

The SMART Notebook Preferences dialogue box appears.

- 2. Press General.
- 3. Clear the Use the shake gesture to group and ungroup objects tickbox.
- 4. Press OK.

To disable the press-and-hold gesture

1. Select Edit > Preferences.

The SMART Notebook Preferences dialogue box appears.

- 2. Press General.
- 3. Clear the Press and hold to perform a right-click tickbox.
- 4. Press OK.

Setting hardware acceleration preferences

Setting image optimisation preferences

If your .notebook files contain large pictures (pictures over 1 MB in file size), your files could open and run slowly. You can reduce the pictures' file size without noticeably reducing their quality. As a result, your .notebook files' overall file sizes will be smaller and the files will open and run more quickly.

To set image optimisation preferences

1. Select Edit > Preferences.

The SMART Notebook Preferences dialogue box appears.

- 2. Press Defaults.
- 3. Select one of the following options in the *Image optimisation* drop-down list:
 - Ask every time I insert a large image to have the option of reducing or not reducing large pictures' file sizes when you insert them.
 - Never change the resolution of inserted images to never reduce large pictures' file sizes when you insert them.
 - Always change image resolution to optimise file size to always reduce large pictures' file sizes when you insert them.
- 4. Press OK.

Manually reducing the size of large pictures

If you selected **Ask every time I insert a large image** in the *Image Optimisation* drop-down list, you can manually reduce the size of large pictures when you insert those pictures in your file or afterwards.

To reduce the size of a large picture when inserting it in a file

1. Insert the picture as described in Inserting pictures on page 77.

After you press **Open**, the *Image Optimisation* dialogue box appears.

Maintaining SMART Notebook software

2. Press **Optimise** to reduce the picture's file size.

OR

Press **Keep Resolution** to not reduce the picture's file size.



NOTES

- When you insert a BMP file, SMART Notebook software internally converts the file to PNG format. This conversion reduces the size of the file. As a result, you might not need to export an optimised version of the .notebook file (see Exporting optimised files below) even if the BMP file is over 1 MB in size.
- SMART Notebook software automatically reduces the file size of pictures over 5 MB or 5 megapixels regardless of which option you choose.

To reduce the size of a large picture after inserting it in a file

- 1. Select the picture.
- 2. Press the picture's menu arrow and then select **Image Optimisation**.

The Image Optimisation dialogue box appears.

3. Click Optimise.

Exporting optimised files

If you have existing files that contain large pictures or if you chose Never change the resolution of inserted images in the Image Optimisation drop-down list, you can export optimised versions of your files that contain reduced pictures. This is particularly useful when you need to present a .notebook file on an older or less powerful computer.

To export an optimised file

1. Select File > Export As > Optimised SMART Notebook File.

The Export Optimised File dialogue box appears.

- 2. Browse to where you want to save the new file.
- 3. Type a name for the file in the *File name* box.
- 4. Press Save.

Setting default background colour preferences

By default, new pages added to your file have a default white background colour. You can change the default background colour.



NOTE

This setting only affects new pages, and will be overridden by any applied Themes.

To change the default background colour


1. Select Edit > Preferences.

The SMART Notebook Preferences dialogue box appears.


- 2. Press Defaults.
- 3. Select Change Colour and then select a colour.
- 4. Press OK.

Setting measurement tool preferences

By default, the ruler, protractor and Geodreieck protractor in SMART Notebook software are blue and display best with light-coloured backgrounds.



You can change these measurement tools' colour to yellow if you want to use them with darkcoloured backgrounds.



NOTE

Completing the following procedure affects the appearance of measurement tools in .notebook files when viewed on your copy of SMART Notebook software only. If you open the same .notebook files on another copy of SMART Notebook software, the measurement tools could display in a different colour.

Maintaining SMART Notebook software

To change the measurement tools' colour

1. Select Edit > Preferences.

The SMART Notebook Preferences dialogue box appears.

- 2. Press Defaults.
- 3. Select Blue tint (recommended for light backgrounds) in the Measurement tool colour drop-down list to set the measurement tools' colour to blue.

OR

Select Yellow tint (recommended for dark backgrounds) in the Measurement tool colour drop-down list to set the measurement tools' colour to yellow.

4. Press OK.

Setting table cell padding preferences

SMART Notebook 11 software adds cell padding to tables.



Table before upgrading to SMART Notebook 11 software (without cell padding)



Table after upgrading to SMART Notebook 11 software (with cell padding)

Complete the following procedure to remove cell padding from tables. This is particularly useful if you created tables prior to upgrading to SMART Notebook 11 software and intended the tables' contents to display without cell padding.



NOTE

Completing the following procedure affects the appearance of tables in .notebook files when viewed on your copy of SMART Notebook software only. If you open the same .notebook files on another copy of SMART Notebook software, the tables display with cell padding (assuming the procedure hasn't been completed on that copy of SMART Notebook software).

To remove cell padding from tables

Select Edit > Preferences.

The SMART Notebook Preferences dialogue box appears.

- 2. Press Defaults.
- 3. Clear the Add cell padding to table cells ticbox.
- 4. Press **OK**.

5. Close and restart SMART Notebook software.

New and existing tables in your .notebook files display without cell padding.

Setting the language

The SMART Language Setup utility enables you to set the language for a specific SMART application or all SMART applications installed on your computer.

To set the language

1. Select Options > Language Setup.

The Language Setup dialogue box appears.

2. Select All Listed Applications in the first drop-down list to set the language for all applications.

OR

Select an application in the first drop-down list to set the language for only that application.

3. Select the appropriate language in the second drop-down list.

NOTES

- If ✓ appears beside your selected language, the language is installed on your computer.
- If appears beside your selected language, the SMART Language Setup utility downloads the language from the website after you press OK.
- o By default, the SMART Language Setup utility uses Internet Explorer Internet browser's settings to connect to the Internet. However, you can use different settings by completing the steps under the next procedure.



To display the languages in their native names (for example, Deutsch for German), select the Show native names tickbox.

4. If you want to use different languages for handwriting recognition and spell checking, select languages in the Handwriting recognition and Spell check drop-down lists.



NOTE

If AUTO appears in the drop-down list, the SMART Language Setup selects your chosen language if available or a similar language if otherwise. If neither option is available, SMART Language Setup selects the current language.

5. If you want to use a different keyboard layout, select a layout in the *Keyboard input language* drop-down list.

IMPORTANT

The *Keyboard input language* drop-down list is available only if there's more than one keyboard layout installed on your computer.

The keyboard layout you select in the *Keyboard input language* drop-down list applies to both the on-screen keyboard and the keyboard connected to your computer when you use SMART software.

In some situations, you might want to select a layout that is different from the layout of the keyboard connected to your computer (for example, to teach a second language). In these situations, the on-screen keyboard works correctly, but the keyboard connected to your computer might not.

For best results, ensure that the layout you select is identical to the layout of the keyboard connected to your computer. For example, if an English (US) keyboard is connected to your computer, select **English (United States)** in this drop-down list.

For information on keyboard layouts, see http://msdn.microsoft.com/en-us/goglobal/bb964651.

6. Press OK.

To set the connection options

Select Options > Language Setup.

The Language Setup dialogue box appears.

2. Press Connection Options.

The Connection Options dialogue box appears.

3. Select Use Internet Explorer settings.

OR

Select **Use other proxy** and then type the host, user name and password in the appropriate boxes.

4. Press OK.

Removing SMART software

SMART Support might ask you to remove existing versions of SMART software before you install new versions. You can do this using the SMART Uninstaller.

To remove SMART software

 In Windows XP and Windows 7 operating systems, select Start > All Programs > SMART Technologies > SMART Tools > SMART Uninstaller.

OR

In Windows 8 operating system, go to the Apps screen and then scroll to and press SMART Uninstaller.

- 2. Press Next.
- 3. Select the check boxes of the SMART software and supporting packages that you want to remove and then press Next.



- Some SMART software is dependent on other SMART software. For example, if you select the SMART Notebook tickbox, SMART Uninstaller selects the SMART Response tickbox automatically because SMART Response software is dependent on SMART Notebook software.
- SMART Uninstaller automatically removes any supporting packages that are no longer being used. If you choose to remove all SMART software, SMART Uninstaller automatically removes all supporting packages, including itself.

TIPS

- To select all software and supporting packages, press Select All.
- To clear the selection of all software and supporting packages, press Clear All.
- 4. Press Uninstall.

SMART Uninstaller removes the selected software and supporting packages.

5. Press Finish.

Updating and activating SMART software

Once you have installed SMART software, you need to activate it. Once you have activated the software, you need to install updates from SMART.



☐ IMPORTANT

To update and activate SMART software, you need to be connected to the Internet.

Updating SMART software

SMART periodically releases updates to its software and firmware products. (Firmware is software installed in hardware products like the SMART Board interactive whiteboard.) You can use SMART Product Update (SPU) to check for and install these updates.

Your system administrator can install SPU in Full mode or Dashboard mode. In Full mode, you can view installed versions and download and install updates as documented in this section. In Dashboard mode, you can only view installed versions.

To check for updates automatically

In Windows XP and Windows 7 operating systems, select Start > All Programs > SMART Technologies > SMART Tools > SMART Product Update.

OR

In Windows 8 operating system, go to the *Apps* screen and then scroll to and press **SMART Product Update**.

The SMART Product Update window appears.

- 2. Select the **Check for updates automatically** tickbox and then type the number of days (up to 60) between SPU checks.
- 3. Close the SMART Product Update window.

If an update is available the next time SPU checks, the SMART Product Update window appears automatically and the Update button of the affected product is enabled.

To check for updates manually

In Windows XP and Windows 7 operating systems, select Start > All Programs > SMART Technologies > SMART Tools > SMART Product Update.

OR

In Windows 8 operating system, go to the *Apps* screen and then scroll to and press **SMART Product Update**.

The SMART Product Update window appears.

2. Press Check Now.

If an update is available for a product, its *Update* button is enabled.

3. If an update is available, install it by following the next procedure.

Maintaining SMART Notebook software

To install an update

- 1. Open the SMART Product Update window as described in the previous procedures.
- 2. Press the product's row.

Product details appear. These product details include the installed version's number and the update's number, date and download size (if an update is available).



Press View release notes to view a summary of the changes in the update and the computer requirements for the update.

- 3. Press Update.
- 4. Follow the on-screen instructions to download and install the update.



IMPORTANT

To install updates, you must have full administrator access.

To disable automatic checking for updates

 In Windows XP and Windows 7 operating systems, select Start > All Programs > SMART Technologies > SMART Tools > SMART Product Update.

OR

In Windows 8 operating system, go to the Apps screen and then scroll to and press **SMART Product Update.**

The SMART Product Update window appears.

2. Clear the Check for updates automatically tickbox.



☐ IMPORTANT

SMART recommends that you do not clear this tickbox.

Activating SMART software

Typically, you activate SMART software after installing it. However, in some situations, you activate the software later. For example, you could be evaluating the software before deciding to purchase it.



NOTES

 As of version 11.1, you don't need to activate SMART Notebook software or SMART Product Drivers. SMART provides you with the right to use this software when you purchase a SMART interactive product.

• If you want to use SMART Notebook software with a device that isn't a SMART interactive product, you must purchase a product key.

Purchasing a product key

For some SMART products, you must purchase a product key from your authorised SMART reseller (smarttech.com/wheretobuy).



If you lose your product key, go to smarttech.com/findproductkey.

Activating SMART software with a product key

Once you have obtained a product key, you can activate SMART software.

To activate SMART software

1. In Windows XP and Windows 7 operating systems, select **Start > All Programs >** SMART Technologies > SMART Tools > SMART Product Update.

OR

In Windows 8 operating system, go to the Apps screen and then scroll to and press **SMART Product Update.**

The SMART Product Update window appears.

2. Press Activate or Manage for the software you want to activate.

The SMART Software Activation window appears.



NOTE

The value in the *Status* column indicates the status for each product:

Value	Description
Installed	The software is installed.
Activated	The software is installed and activated with a perpetual or maintenance licence.
Subscription	The software is installed and activated with a subscription licence. The number in parentheses indicates the days remaining in the subscription period.
Expiring	The software is installed but not yet activated. The number in parentheses indicates the days remaining in the evaluation period.
Expired	The software is installed but not yet activated. The evaluation period is over. You're unable to use the software until you activate it.
Unknown	The software's status is unknown.

Maintaining SMART Notebook software

- 3. Press Add.
- 4. Follow the on-screen instructions to activate the software using the product key.

To view product keys

 In Windows XP and Windows 7 operating systems, select Start > All Programs > SMART Technologies > SMART Tools > SMART Product Update.

OR

In Windows 8 operating system, go to the Apps screen and then scroll to and press **SMART Product Update.**

The SMART Product Update window appears.

2. Select Tools > View Product Keys.

The Product Keys dialogue box appears.

3. Press **OK** when you've finished viewing the product keys.



NOTE

Alternatively, you can view the product keys for a single product by pressing the product's name in the SMART Product Update window and then pressing View product key.

Sending feedback to SMART

When you start SMART software for the first time, a dialogue box may appear asking whether you want to join the SMART Customer Experience Programme. If you choose to join the programme, the software sends information to SMART that helps us to improve the software for future releases. After starting the software for the first time, you can enable or disable this feature through the Help menu.

You can also send feature request emails to SMART.

- To enable the Customer Experience Programme tracking feature
 - Select Help > Customer Experience Programme > Feedback tracking ON.
- To disable the Customer Experience Programme tracking feature

Select Help > Customer Experience Programme > Feedback tracking OFF.

- To send a feature request email
 - 1. Select Help > Submit Feature Request.

A new email message appears in your default email program.

2. Type your request in the new email message and then press **Send**.

Chapter 14

Troubleshooting SMART Notebook software

Troubleshooting files	171
Troubleshooting the SMART Notebook software window and toolbar	171
Troubleshooting digital ink	172
Troubleshooting objects	173
Troubleshooting gestures	174

This chapter explains how to troubleshoot issues with SMART Notebook software.

Troubleshooting files

Issue	Recommendation
Your file contains large pictures and runs slowly when you open it in SMART Notebook software.	Export an optimised version of the file (see Setting image optimisation preferences on page 159).

Troubleshooting the SMART Notebook software window and toolbar

Issue	Recommendation	
When using SMART Notebook software on an interactive product, you or your students can't reach the toolbar.	Press Move toolbar to top/bottom of window to move the toolbar from the top of the window to the bottom.	
	If you have a height-adjustable wall mount, you can also adjust the height of your interactive whiteboard or display so that students can reach it.	

Issue	Recommendation
Toolbar buttons described in this documentation don't appear on the toolbar.	If a down arrow ▼ appears on the right side of the toolbar, press it to display additional toolbar buttons. If your desired button doesn't appear when you click the down arrow ▼, you or another user might have removed the button (see Customising the toolbar on page 155). Don't span more than a few buttons across rows to prevent the toolbar from being wider than the SMART Notebook software window.
There isn't enough room on your interactive product to display the contents of a page.	Press View Screens and then select Full Screen to display the page in Full Screen mode. OR Select the Auto-hide tickbox to hide the tabs when not in use.
The Page Sorter, Gallery, Attachments, Properties and other tabs disappear whenever you press outside of the tabs.	Press one of the tab's icons to display it and then clear the Auto-hide tickbox.
Two users are creating or manipulating objects in SMART Notebook software on a SMART Board 800 series interactive whiteboard. One user is using his or her finger. The other user is using a pen from the pen tray. When the user using the pen presses a button in the toolbar, the selected tool or option changes for the user using his or her finger instead.	The user using the pen must press buttons in the toolbar with the pen, not with his or her finger. For more information, see <i>Enabling two people to use a SMART Board 800 series interactive whiteboard</i> on page 144.

Troubleshooting digital ink

Issue	Recommendation
SMART Notebook software doesn't recognise handwriting in your language.	Install the appropriate language pack (see Setting the language on page 163).
You want your handwriting to appear more smooth and natural in SMART Notebook software.	Use the Calligraphic pen type rather than the Standard pen type (see Writing or drawing digital ink on page 32).
You're having trouble writing smoothly in SMART Notebook software on Windows 7 operating system.	The Single Finger Panning feature is turned on. Turn it off (see smarttech.com/kb/147470).
When you write with a pen, SMART Notebook software on Windows 7 operating system interprets your actions as mouse clicks.	The Flicks feature is turned on. Turn it off (see smarttech.com/kb/144274).

Troubleshooting objects

Issue	Recommendation			
When you create a .notebook file on one computer and then open it on another computer, the objects in the file appear differently.	 There are several possible causes. The following are the most common: You used a font that's installed on one computer but not on the other. The two computers have different operating systems. The two computers have different versions of SMART Notebook software. 			
You want to move, resize or otherwise change an object, but when you do so, you also move, resize or otherwise change other objects.	The objects are grouped. Any changes you make to one object affect the other objects. Select the objects and then select Format > Group > Ungroup to ungroup them. You can then move, resize or otherwise change the individual objects. For more information, see <i>Grouping objects</i> on page 68.			
You want to move, resize or otherwise change an object but can't. A lock icon appears instead of a menu arrow when you select the object.	making changes to it. To unlock the object,			
One object on a page covers another:	As you create objects, newer objects cover older objects automatically if the objects are in the same position on the page. You can change the order of objects. For more information, see <i>Rearranging stacked objects</i> on page 61.			
You want to change this so that the second object covers the first:				

Issue	Recommendation
When you fill an object with a picture that is larger than the object, the picture is cut off: Conversely, when you fill an object with a picture that is smaller than the object, the picture is tiled:	When filling an object with a picture, select Scale image to fit to resize the picture to fit the object: For more information, see Changing objects' properties on page 55.

Troubleshooting gestures

Issue	Recommendation
The multitouch gestures described in this guide aren't working in SMART Notebook software.	Ensure that your interactive product supports multitouch gestures and that multitouch gestures are enabled.

Index

A	pages 25
	compasses 139
activation 167	content
Activity Builder 110	inserting in .notebook files 71
add-ons	organising 92
about 147	sharing with other teachers 93
disabling 148	Crayon pen type 32
identifying missing 148	Creative pen type 33, 98
installing 147	cropping
removing 149	images 63
using 148	crosses 35
Adobe Flash Player compatible files 79	Customer Experience Programme 169
Adobe Flash video files 80	
AIFF files 81	D
animation 103	_
arcs 37	default program for .notebook files 157
arrows 35	diamonds 35
ASF files 81	digital ink
attachments 89	about 32
audio encoders 81	converting to text 39, 131-132
audio files See sound files	erasing 34
automatic tasks	troubleshooting 172
grouping objects 70	writing or drawing 32
saving 18	document cameras 78
AVI files 81	downloads 81
	drop cap 41
В	Dual-User mode 144
_	Dual Page view 123
backgrounds 106	
BMP files 15, 20, 77, 160	F
bold text 41	_
bold text 41	
C	email 21
C	encoders 81
	eraser 34
Calligraphic pen type 32	Essentials for Educators See Gallery
cell padding 162	Essentials
CFF files 17, 85	exports 15, 94
circles 35, 37	-
cloning	F
objects 64	
	fading objects 128, 133

feature request emails 169	gestures
feedback 169	about 9
files	setting preferences for 158
attaching to .notebook files 89	troubleshooting 174
attaching to email messages 21	types of
creating 13	flick 59
cutting, copying, and pasting content	panning 120
from 81	pinch to zoom 119
displaying in Dual-User mode 144	rotate 67
displaying in Dual Page view 123	scale 65
displaying in Full Screen view 120	shake 69, 158
displaying in Transparent Background	swipe 23
view 122	GIF files 15, 20
exporting 15	graphics See pictures
importing 82-83, 85	groups
linking to objects 101	object 68, 173
opening 13	pages 27
printing 17	
reducing size of 159	Н
saving 14	• •
saving automatically 18	handouts 17
troubleshooting 171	handwriting, conversion to text of 39, 131-
Flash files See Adobe Flash Player	132, 163
compatible files	headers 16-17
Flash video files See Adobe Flash video	heptagons 36
files	hexagons 35-36
footers 16-17	highlighter 32
freehand objects See digital ink	HTML files 15
Full Screen view 120	TITIVIL IIIES 13
	1
G	1
O-H	images See pictures
Gallery	imports 82-85, 93
adding themes to 109	Interactive Whiteboard Common File
adding your content to 91	Format 17, 85
applying backgrounds and themes from 108	Internet browsers 87
exporting content from 94	invisible areas See transparent areas
finding and working with content from 71	italicised text 41
importing content to 93	
organising your content in 92	J
Gallery Essentials 71	
Gallery Sampler See Lesson Activity	JPEG files 15, 20, 77
Examples	
Geodreieck protractors 137	K
GeoGebra	
finding and working with content from 75	keyboards 164
	keyboards 164

Notebook software See SMAR		
languages 39, 131-132, 163	O	
Lesson Activity Examples 71		
Lesson Activity Toolkit 71	objects	
lines 37	adding links to 100	
links	adding to tables 46	
adding to objects 100	adding to the Gallery 91	
showing 124	aligning 60	
Linux operating systems 14	animating 103	
locked objects 103, 173	clearing all from a page 141	
•	cloning 64	
M	cropping 63	
	cutting, copying and pasting 62	
Mac OS V apprating quatern aeftware 14	deleting 70	
Mac OS X operating system software 14	erasing 34	
Magic pen tool 33	fading 128, 133	
Magic Pen tool 127	flipping 68	
magnification 119, 128	grouping 68	
mathematical symbols 42	locking 103	
maths editor 86	moving 58	
measurement tools	moving to other pages 59	
about 133	rearranging 61	
setting preferences for 161	resizing 65	
types of	resizing text 42	
compass 139	rotating 67	
Geodreieck protractor 137	selecting 53	
protractor 135	setting fill and line style for 55	
rulers 133	troubleshooting 173	
MediaCoder 81	octagons 36	
menu arrows 54	online resources 76	
MOV files 81	ovals 37	
MP3 files See sound files	Ovais 31	
MPEG files 81	D	
multimedia files 79	The state of the s	
multiple interactive products 125		
music files See sound files	padding 162	
My Content category 92, 94, See	page numbers 16-17	
also Team Content categories	pages	
N.I.	adding to the Gallery 91	
N	clearing 141	
	cloning 25	
names	creating 24	
of files 14, 160	deleting 28	
of page groups 27	displaying 23	
of pages 26	displaying in Dual-User mode 144	
.notebook file format 14, 157	displaying in Dual Page view 123	
	displaying in Full Screen view 120	

displaying in Transparent Background	preferences
view 122	gestures 158
extending 25	image optimisation 159
grouping 27	measurement tools 161
hiding with Screen Shades 126	table cell padding 162
linking to objects 100	Preferences
moving objects between 59	new page default colour 160
panning 120	printers 17, 82-83
pinning 123	product keys 167
printing 17	protractors 135
rearranging 26	proxy servers 88
recording 105	
renaming 26	Q
setting backgrounds for 106	
zooming in and out 119	QuickTime files See MOV files
Paint Brush pen type 33	Quick Time mad Coo We v mad
panning 120	R
parallelograms 35	
PDF files	
attaching to email messages 22	rectangles 35, 37
exporting 16	regular polygons 36
pens	resize handle 65
types of	RSS feed 151-153
Calligraphic 32	rulers 133
Crayon 32	0
Creative 33, 98	S
Highlighter 32	
Magic 33, 127	scanners 77
Paint Brush 33	Screen Shades 126
Shape Recognition 33, 37	set squares See Geodreieck protractors
Standard 32	Shape Recognition Pen tool 33, 37
Text 33	shapes
pentagons 35-36	about 35
photographs See pictures	creating with the Regular Polygons tools 36
pictures	creating with the Shape Recognition Pen
about 77	tool 37
creating transparent areas in 78	creating with the Shapes tool 35
exporting files to 16	shortcuts 89
inserting from a scanner 77	Single-User mode 144
inserting from a SMART Document	SMART Board 800 series interactive
Camera 78	whiteboards 144
inserting from files 77	SMART Board D600 series interactive
reducing file sizes of 159	whiteboards 144
PNG files 15, 20, 77	SMART Board Tools 2
polygons 36	SMART Document Cameras 78
PowerPoint 16, 46, 84	SMART Exchange 76, 95, 147

SMART Ink	creating 109
about 2	thumbnails
SMART Notebook 2	in printouts 17
SMART Notebook Document Writer 83	in the Page Sorter 23
SMART Notebook Print Capture 82	ticks 35
SMART Product Drivers 2	TIFF files 77
SMART Product Update 165	tool change notifications 9
SMART Uninstaller 164	toolbars
sound files 102, 125	Full Screen 121
spell checker 43, 163	SMART Notebook 155, 171
spotlight 130	Transparent Background 122
squares 35-37	transparent areas 78
stacks of objects 61	Transparent Background view 122
straight lines 37	trapezoids 35
SWF files See Adobe Flash Player	triangles 35-37
compatible files	troubleshooting
compatible mes	digital ink 172
T	files 171
1	gestures 174
	objects 173
T-squares See Geodreieck protractors	SMART Notebook software window and
tables	toolbar 171
about 44	toolbai 171
adding cell shades to 126	11
adding columns, rows or cells to 51	U
adding objects to 46	
changing properties for 48	underlined text 41
creating 44	updates 165
moving 48	X //
removing 52	V
removing cell padding from 162	
removing cell shades from 126	video encoders 81
removing columns, rows or cells from 51	videos 80
selecting 47	volume 125
splitting or merging cells in 52	
Team Content categories See also My	\/\
Content category	VV
text)
checking spelling of 43	WAV files 81
converting handwriting to 39, 131-132	web browsers See Internet browsers
cutting 44	webpages 15, 90, 100
editing 40	widgets 76
including mathematical symbols in 42	Windows Media files 81
resizing 42	Windows operating systems 14
typing 38	WMF files 77
Text pen type 33	Word 46
themes	
applying 108	



XBK files 13

Z

zooming in and out 119, 128